

Don't see what you're looking for? Log in for the full Help Center experience

Whitebit account

Updated 8 months ago

Configuring your Whitebit account

To configure your Whitebit account to connect to Fireblocks:

1. Refer to the [Whitebit.com API Documentation](#) to learn how to generate an API key.
2. Make sure that in the Whitebit platform you create the API Key from within the **Fireblocks Integration section**, and NOT from the **API Key section**. In order to gain access to the Fireblocks Integration section, you must open a ticket with Whitebit's support team.
3. When prompted to do so, name your new API Key "Fireblocks."
4. After you confirm the validity of your new API key, copy and keep a record of both the API Key and API Secret. You will need them when adding this exchange to your workspace.
5. Under IP addresses, delete the 0.0.0.0 address and then add the following IP address: 52.76.208.129.

Configuring Fireblocks

1. Go to **Accounts > Exchanges**.
2. Select **+ Connect Account**.
3. Select **Whitebit**, and then complete the following fields:
 - a. **Name on Fireblocks**: Enter the name you want to give this exchange account on Fireblocks.
 - b. **API Key**: Enter the API key that you saved from Whitebit.
 - c. **API Secret**: Enter the Secret key that you saved from Whitebit.
 - d. Select **Connect Account**.

Note:

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center



from your workspace.

Your Whitebit account will be displayed on the Exchanges page along with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault accounts, whitelisted addresses, Fireblocks P2P Network connections, and other connected exchange accounts to your Whitebit account. Withdrawals from your Whitebit account are permitted after you whitelist your Fireblocks account's address on Whitebit.

Enabling withdrawals from Whitebit

To enable exchange account withdrawals, see [this procedure](#).

Transferring assets

You can transfer assets to your Whitebit account from vault accounts, other exchanges, and Fireblocks P2P Network members. To withdraw from your Whitebit account to any destination in Fireblocks, add the deposit address to your Whitebit Wallet Address Book as described above. Learn more about [transferring assets](#).

Was this article helpful?

Yes

No

ON THIS PAGE

Configuring your Whitebit account

Configuring Fireblocks

Enabling withdrawals from Whitebit

Transferring assets

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)