

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

Search the Help Center /

Set up your Fireblocks Vault with Key Link

Updated 6 months ago


The Fireblocks Vault is the secure wallet storage solution for safely managing your assets and client funds. Learn more in the [Fireblocks Vault article](#).

In your Fireblocks Key Link workspace, each vault account can be assigned one ECDSA and one EdDSA key. Once a key is assigned to a vault account, it cannot be used in other vault accounts.

The key assignment to a vault account can be done automatically to offer a more seamless experience. If you would like to assign a key manually to a vault account, you can do so by creating a vault account without the automatic key assignment option and following the [instructions](#) below.

Automatic key assignment

When you create a vault account in the Fireblocks Console, an automatic key assignment option appears only when there are available keys in your workspace to be assigned.



Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

vault accounts), this option will not be available, but you can create a new vault account without any keys assigned. When new keys become available in the workspace, you can assign them manually to the vault account by following the instructions in the [Manual Key Assignment](#) section below or by using the [Key Management Dashboard](#).

Manual key assignment

You can assign keys to vault accounts using either the Key Management Dashboard or the API.

Using the Key Management Dashboard

1. Navigate to **Settings > External Keys**.
2. Go to the **Signing keys** tab.
3. Find an available key and click the **Manage** button.
4. Assign the key to your preferred vault.

Alternatively, from the vault account page:

1. Go to **Accounts** and select your vault account.
2. Click **Assign key**.
3. Select an available key from the list.

For detailed instructions, see [Managing Keys with the Key Management Dashboard](#).

Using the API

To assign an available key to a vault account using the API:

1. Check the list of available keys in your workspace using the [Get signing keys](#) API endpoint.
2. Assign a key to a vault account with the [Modify signing keyId](#) API endpoint, by specifying the vault account to which you want to assign the key.

Creating asset wallets

Once you have created your vault account, you can [create asset wallets](#). Once done, you can start receiving funds and create transactions to be signed by your HSM.

Note

To create a specific asset wallet in the vault account, you must have an assigned key with the algorithm (ECDSA, or EdDSA) required by that asset's underlying protocol.

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center

/

Create asset wallet Vault 123

**ETC_TEST**
Ethereum Classic Test

**XLM**
Stellar

**XLM_TEST**
Stellar Test

**DAI**
Dai (Ethereum)

**TUSD**
Tether USD (Ethereum)

Requires EdDSA key

Requires EdDSA key

i Each vault account can hold 1 wallet per asset.

! There is no EdDSA key assigned to the vault account.
Add an EdDSA key via the Fireblocks API and assign it to the vault account to create an asset wallet that requires one. [Learn more](#)

[Cancel](#) [Create wallet](#)

Learn more about [Monitoring your Key Link stats](#).

Was this article helpful?

Yes

No

Related Articles

 [Troubleshooting incomplete user setup](#)

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

