

Don't see what you're looking for? Log in for the full Help Center experience

Binance sub-account

Updated 4 months ago

Overview

Fireblocks supports Binance sub-accounts via exchange connectivity. Connect the accounts, and rebalance securely between your exchange's main account and sub-accounts on Fireblocks.

Important

- If you have a Binance sub-account connected to this workspace that isn't connected to a main account, you must remove and reconnect it.
- If you have a Binance main account connected, you may need to remove it if the email field was left blank.

Configuring your Binance sub-account

To configure your Binance sub-account to connect to Fireblocks:

1. Refer to the [Binance.com API Documentation](#) to learn how to generate a Binance API key for the following sub-account types:
 - [Portfolio Margin*](#)
 - [Futures Lead Trading Portfolio](#)
 - [Spot Lead Trading Portfolio](#)
2. When prompted, name your new API Key "Fireblocks."
3. After you confirm the validity of your new API key, copy and keep a record of both the API Key and Secret Key. You will need them when adding this exchange to your workspace.
4. Enable the following API Restrictions:
 - **Reading**
5. Enable the sub-account type you are connecting to the main account:
 - **Spot & Margin Trading**

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

- 8.133.153.74 18.158.242.74 3.10.103.242 3.10.68.107 3.64.123.47 3.67.233.15
18.98.161.0 18.98.161.1 18.98.161.2 18.98.161.3 18.98.161.4 18.98.161.5
18.98.161.6 18.98.161.7 18.98.161.8 18.98.161.9 18.98.161.10 18.98.161.11
18.98.161.12 18.98.161.13 18.98.161.14 18.98.161.15 18.98.161.16 18.98.161.17
18.98.161.18 18.98.161.19

*The [Binance Portfolio Margin Pro Program](#) is not currently supported in Fireblocks.

Configuring Fireblocks

1. In the Fireblocks Console, go to **Accounts > Exchanges**.
2. Select **+ Connect Account**.
3. Select **Binance**, select Sub account, and then complete the following fields:
 - a. **Account Name:** Enter the name you want to give this exchange sub-account in your workspace.
 - b. Select the main account you want to connect to this sub-account.
Remember, your main account must be connected to Fireblocks *before* you can connect a sub-account.
 - c. **API Key:** Enter the API key that you saved from Binance.
 - d. **Secret Key:** Enter the Secret key that you saved from Binance.
 - e. **Email:** Enter the email account you used to register your Binance account.
4. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Binance sub-account is displayed on the Exchanges page with all managed assets and their balances. Following Admin Quorum approval, you can transfer assets between this sub-account and its Binance main account.

Binance sub-account transfers

Fireblocks supports direct transfers between Binance sub-accounts that belong to the same Binance main account.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

transferring assets between sub-accounts.

Key characteristics of sub-account transfers

- Transfers are off-chain
- Source and destination sub-accounts must belong to the same Binance main account
- No blockchain fees are incurred
- Transfers are subject to Binance permissions and Fireblocks policy rules

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Configuring your Binance sub-account

Configuring Fireblocks

Binance sub-account transfers

Related Articles

-  Coinbase Pro and Coinbase Exchange sub-accounts
-  Crypto.com sub-account
-  Coinhako sub-account
-  Deribit sub-account
-  Gate.io sub-account
-  HTX (formerly Huobi) sub-account
-  Kraken, Kraken Futures and Kraken International sub-accounts
-  KuCoin sub-account

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center



-  [Binance account](#)
-  [Bitfinex sub-account](#)
-  [Binance.US sub-account](#)
-  [Binance.US account](#)
-  [Bitget sub-account](#)



[fireblocks.com](#) [Status](#) [API Docs](#) [Console](#) [info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)