

Don't see what you're looking for? Log in for the full Help Center experience

BitMEX account

Updated 8 months ago

Configuring your BitMEX account

To configure your BitMEX account to connect to Fireblocks:

1. Refer to the [bitmex.com API Documentation](#) to learn how to generate an API key.
2. When prompted to do so:
 - Name your new API Key "Fireblocks."
 - Enter 52.76.208.129/32 in the **CIDR** field.
 - Check the **Withdraw** checkbox.
 - If enabled, enter your 2FA code into the **Two-factor Token** field.
3. After you confirm the validity of your new API key, copy and keep a record of both the ID and Secret. You will need them when adding this exchange to your workspace.
4. Make sure you enable 2FA via **Google Authenticator**. Copy and keep a record of the **Google Authenticator Code**, which will later fit into the **Two-factor token**. You will need it when adding this exchange to your workspace.
5. Once you enter the Two-factor token, you are requested to confirm the **TOTP token**. This token is essential for completing the exchange integration if your BitMex account is configured with a 2FA. The TOTP is the 2FA master key and is accessible only when you set up your 2FA, so you must save it, otherwise, you will not have access to it, and will need to reset your 2FA on BitMex's side in order to get a new one. Also note that after you set up a new 2FA on BitMEX (or reset your 2FA), your withdrawals are blocked for 24 hours. For more info on how to enable 2FA on BitMex, [go here](#).

Configuring Fireblocks

1. In the Fireblocks Console, go to **Accounts > Exchanges**.
2. Select **+ Connect Account**.
3. Select **BitMEX**, and then complete the following fields:

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



e. Select **Connect Account**.

Note:

The "+ Connect Account" is relevant only if you have an existent exchange account connected to Fireblocks and would like to add another one. If this is your first exchange account connection, add it by selecting "Connect Account" under the Exchanges tab.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your BitMEX account appears on the Exchanges page along with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault accounts, whitelisted addresses, Fireblocks P2P Network connections, and other connected exchange accounts to your BitMEX account.

Enabling withdrawals from BitMEX

To enable exchange account withdrawals, see [this procedure](#).

Was this article helpful?

Yes

No

ON THIS PAGE

Configuring your BitMEX account

Configuring Fireblocks

Enabling withdrawals from BitMEX

Fireblocks

fireblocks.com

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center

