

Don't see what you're looking for? Log in for the full Help Center experience

Bitget account

Updated 8 months ago

Configuring your Bitget account

To configure your Bitget account to connect to Fireblocks:

1. Refer to the [Bitget API Documentation](#) to learn how to generate a Bitget API key.
2. When prompted to do so, name your new API Key “Fireblocks.”
3. After you confirm the validity of your new API key, copy and keep a record of both the API Key and API Secret. You will need them when adding this exchange to your workspace.
4. Make sure you enable the following permissions in **Read-write** mode:
 - Futures > **Orders, Holdings**
 - Spot > **Trade**
 - Margin > **Trade**
 - Wallet > **Transfer, Withdraw**
 - Sub-accounts > **Manage**
5. Under the **Link IP address** field, enter: **18.117.33.242**.
6. Under IP access restrictions, enter **52.76.208.129** in place of 0.0.0.0.

Below is a list of assets supported by Bitget on Fireblocks:

Symbol	Blockchain
BTC	Bitcoin
ETH	Ethereum
USDC	Ethereum
USDT	Ethereum
USDT	Tron
XRP	Ripple

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

- a. **Name on Fireblocks:** Enter the name you want to give this exchange account on Fireblocks.
- b. **API Key:** Enter the API key that you saved from Bitget.
- c. **API Secret:** Enter the Secret key that you saved from Bitget.

4. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Bitget account is displayed on the Exchanges page, with all managed assets and their balances. Following Admin Quorum approval, transfers are available between your Bitget account and your vault accounts, exchange accounts, whitelisted addresses, and Fireblocks P2P Network connections.

Enabling withdrawals from Bitget

To enable withdrawals from your Bitget account, you may need to [whitelist an address in your Bitget address book](#). [Learn more about enabling exchange account withdrawals in Fireblocks](#).

Bitget sub-accounts

[Learn more about adding a Bitget sub-account](#).

Was this article helpful?

Yes

No

ON THIS PAGE

■ [Configuring your Bitget account](#)

[Enabling withdrawals from Bitget](#)

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

-  Luno account
-  N3XT Account
-  Yellow Card Account
-  Bullish account
-  Coinbase international account
-  Gemini V2 Account
-  Bitget sub-account
-  Setting Up Travel Rule Support
-  Bridge account



[fireblocks.com](#) [Status](#) [API Docs](#) [Console](#) info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)