

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Coinbase Prime account

Updated 8 months ago

Configuring your Coinbase Prime account

To configure your Coinbase Prime account to connect to Fireblocks:

1. Refer to the [Coinbase Prime API Documentation](#) to learn how to generate an API key.
2. When prompted to do so, name your new API Key "Fireblocks."
3. After you confirm the validity of your new API key, copy and keep a record of the following items, as you will need them when adding this exchange to your workspace:
 - API Key
 - Secret key
 - Passphrase
 - Portfolio ID*
4. Under IP access restrictions, add the following IP address: 52.76.208.129.

Note:

The Portfolio ID can be found in the URL when you log into your Coinbase Prime Portfolio, as shown in the image below. This ID is separate from your Service Account ID, which is not needed to connect to Fireblocks.



Configuring Fireblocks

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

ACCOUNT ON FIREBLOCKS.

- b. **API Key**: Enter the API key that you saved from Coinbase Prime.
- c. **Secret Key**: Enter the Secret key that you saved from Coinbase Prime.
- d. **Passphrase**: Enter the passphrase that you saved from Coinbase Prime.
- e. **Portfolio ID**: Enter the Portfolio ID that you saved from Coinbase Prime.
- f. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Coinbase Prime account appears on the Exchanges page along with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault accounts, whitelisted addresses, Fireblocks P2P Network connections, and other connected exchange accounts to your Coinbase Prime account.

Enabling withdrawals from Coinbase Prime

See the [Coinbase Prime documentation](#) to learn more about managing your portfolio address book.

[Learn more about enabling exchange account withdrawals in Fireblocks.](#)

Was this article helpful?

Yes

No

ON THIS PAGE

Configuring your Coinbase Prime account

Configuring Fireblocks

Enabling withdrawals from Coinbase Prime

Related Articles

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center





[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

[info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)