

Don't see what you're looking for? Log in for the full Help Center experience

Coinbase Pro and Coinbase Exchange account

Updated 8 months ago

Overview

Coinbase Exchange is a business-facing solution by Coinbase that enables trading. Coinbase Prime is a prime brokerage solution that requires a separate connection on Fireblocks.

Configuring your Coinbase Pro or Coinbase Exchange account

To configure your Coinbase Pro or Coinbase Exchange account to connect to Fireblocks:

1. Refer to the [Coinbase Pro Documentation](#) or the [Coinbase Exchange Documentation](#) to learn how to generate an API key.
2. Copy and keep a record of your passphrase. You'll need it when adding this account to your workspace.
3. Copy and keep a record of both the API Key and Secret Key. You will need them when adding this exchange to your workspace.
4. Make sure you enable the following permissions:
 - **View**
 - **Transfer**
 - **For Sub-accounts, you will also need to add:**
 - **Trade**
 - **Manage**
5. Whitelist the following IP addresses: **40.87.67.58, 40.117.39.160, 52.76.208.129**

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

2. Select **+ Connect Account**.
3. Select **Coinbase Pro** or **Coinbase Exchange**, select **Main Account**, and then complete the following fields:
 - a. **Name on Fireblocks**: Enter the name you want to give this exchange account on Fireblocks.
 - b. **API Key**: Enter the API key that you saved from Coinbase.
 - c. **API Secret**: Enter the Secret key that you saved from Coinbase.
 - d. **Passphrase**: Enter the Passphrase that you created in Coinbase.
 - e. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Coinbase account appears on the connected accounts page along with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault accounts, whitelisted addresses, Fireblocks P2P Network connections, and other connected accounts to your Coinbase account.

Note:

When transferring funds from a third-party exchange to Coinbase, whitelisting restrictions must be removed on the source exchange, or alternatively a whitelisted address must be created.

Enabling withdrawals from Coinbase

See the [Coinbase Exchange documentation](#) to learn more about managing your address book.

[Learn more about enabling exchange account withdrawals in Fireblocks.](#)

Coinbase sub-accounts

[Learn more about connecting a Coinbase sub-account.](#)

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

ON THIS PAGE

Overview

Configuring your Coinbase Pro or Coinbase Exchange account

Configuring Fireblocks

Enabling withdrawals from Coinbase

Coinbase sub-accounts

Related Articles



Coinbase international account



fireblocks.com

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)