

Don't see what you're looking for? Log in for the full Help Center experience

Coinbase Pro and Coinbase Exchange sub-accounts

Updated 5 months ago

Overview

Connect Coinbase main and sub-accounts to rebalance securely between them in your Fireblocks workspace.

Important

Changes in your Policies may be required to support sub-account transfers.

Configuring your Coinbase sub-accounts

To configure your Coinbase sub-account to connect to Fireblocks:

1. Refer to the [Coinbase Pro Documentation](#) or the [Coinbase Exchange Documentation](#) for instructions on how to create an API key.
2. Make sure you enable the following permissions:
 - a. **View**
 - b. **Transfer**
3. Whitelist the following IP addresses: **40.87.67.58, 40.117.39.160, 52.76.208.129**
4. Copy and keep a record of your Passphrase. You will need it when adding this exchange to your workspace.
5. Copy and keep a record of the Secret Key. You will need it when adding this exchange to your workspace.

Configuring Fireblocks

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Fireblocks Help C

/

- a. Enter the name you want to give this exchange sub-account in your workspace.
- b. Select the main account you want to connect to this sub-account.
Remember, your main account must be connected to Fireblocks *before* you can connect a sub-account.
- c. **API Key**: Enter the API key that you saved from Coinbase.
- d. **Secret Key**: Enter the Secret key that you saved from Coinbase.
- e. **Passphrase**: Enter the Passphrase that you created in Coinbase.
- f. Paste the portfolio nickname previously created in Coinbase into the **Sub-Account Name on Coinbase Pro** or **Sub-Account Name on Coinbase Exchange** fields.
- g. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Coinbase sub-account will be displayed on the "Connected Accounts" page, along with all managed assets and their corresponding balances. Following Admin Quorum approval, transfers will be available between this sub-account and its Coinbase main account.

Was this article helpful?

Yes

No

ON THIS PAGE

Overview

Configuring your Coinbase sub-accounts

Configuring Fireblocks

Related Articles

 [Coinbase chain is now supported \(August 2023\)](#)

 [Bitstamp sub-account](#)

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

-  Deribit sub-account
-  Gate.io sub-account
-  HTX (formerly Huobi) sub-account
-  Bitget sub-account
-  Binance.US sub-account
-  Binance sub-account
-  Bitfinex sub-account
-  Kraken, Kraken Futures and Kraken International sub-accounts
-  KuCoin sub-account
-  OKX (OKEx) - API V5 sub-account
-  Coinbase Prime account



fireblocks.com [Status](#) [API Docs](#) [Console](#) info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)