

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

Connected accounts and balances

Updated 13 days ago

Use connected provider accounts to monitor balances, deposit and withdraw funds, transfer between account types, and manage collateral through Off-Exchange. Connected accounts include main accounts, sub-accounts, trading accounts, fiat accounts, and Off-Exchange accounts.

All connected provider accounts appear on the **Connected Accounts/Fiat** page in the Console.

Connected account types

Main accounts

Main accounts are the primary connection to each provider. They support:

- Deposits and withdrawals
- Transfers to and from Fireblocks vault accounts
- Rebalancing across sub-accounts and trading accounts

Key rules:

- You must connect the main account before connecting sub-accounts
- All deposits and withdrawals must flow through the main account
- Providers may require you to whitelist your vault address or other destinations
- You may need to adjust workspace Policies to allow provider-to-provider or external withdrawals

Sub-accounts

Sub-accounts allow you to segment funds by team or strategy.

- Sub-accounts are usually funded through the main account
- Withdrawals must typically route through the main account
- Transfers between main ↔ sub-accounts are off-chain and do not incur network fees
- Transfers between sub-accounts may not be supported

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

Trading accounts include spot, margin, derivatives, futures, and options accounts.

Fireblocks provides visibility and rebalancing support for trading accounts.

- Deposit funds into a main or sub-account first, then transfer to trading accounts
- Transfers between trading accounts and the main account are off-chain and do not incur network fees
- Some providers require enabling trading in the API settings
- Trading account balances appear under each provider on the **Accounts** page

(Provider-specific trading account mappings are available in the *Account Types and Provider Features Glossary*.)

Fiat accounts

Connected fiat accounts support:

- Balance monitoring
- Transfers to Fireblocks P2P Network peers

Connecting a provider account

For provider-specific connection requirements and supported account types, see the [Integrated exchange accounts article](#).

Use the following general steps to connect provider accounts:

1. Generate API credentials

- Create an API key and secret in the provider portal
- Enable required permissions (for example: Read/Write, Withdrawals, Spot, Margin, Futures)

2. Restrict access

- Whitelist Fireblocks IP addresses and remove any open access entries

3. Connect in Fireblocks

- In the Console, go to **Accounts > Connected Accounts/Fiat**
- Select the provider and enter the credentials

4. Request approval

- The [Admin Quorum](#) or an [Approval Group](#) must approve the connection

5. Verify the account

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

View balances

- All connected provider accounts appear on the **Connected Accounts/Fiat** page
- Assets held in main accounts and sub-accounts also appear in aggregated balances and on the [My Assets page](#)
- **Asset representation:** Assets held in connected accounts are often represented by a single balance that can be transferred via multiple blockchain networks.
- **Network Selection:** When transferring these assets, you must select the appropriate network from the drop-down menu in the transfer dialog.
- **Visibility Constraints:** Assets in sub-accounts or trading accounts may not appear on the My Assets page, depending on the specific provider's API capabilities.

Withdraw funds

Withdrawal flow

Withdrawing funds from a provider account to a vault account or external destination includes the following steps:

1. Submit a withdrawal request in Fireblocks.
2. Approve the request on your mobile device according to your [workspace Policies](#).
 - Approval is only required because the provider is the source of funds.
3. The provider broadcasts the transaction to the blockchain.

Whitelisting addresses

Most providers require you to whitelist withdrawal destinations.

To whitelist a vault address:

1. In the Console, go to **Accounts > Vault**.
2. Open the vault account.
3. Select **See Deposit Addresses** for the asset.
4. Copy the address and paste it into the provider's whitelist or address book.

To whitelist a Fireblocks external whitelisted address:

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Fireblocks Help C

/

Notes:

- Some providers may enforce a delay of up to 48 hours when enabling a new whitelisted address
- Bitcoin and some other assets support multiple address types; use the [legacy address](#) when required
- Withdrawals to external wallets or one-time addresses do not generate a network record or transaction ID in Fireblocks, because the source and destination are outside Fireblocks' custody
- Withdrawals must route through the main account. Sub-account > Main > Destination.

Deposit funds

Deposit flow

Depositing funds from your vault to a provider account includes the following steps:

1. Submit a deposit request in Fireblocks.
2. Sign the transaction on your mobile device or using an API Co-Signer.
 - Signing is required because Fireblocks is the source of funds.
3. Fireblocks broadcasts the transaction on-chain.

Deposit rules

- Deposits must flow through the main account.
- Some providers enforce minimum deposit amounts. Deposits below the threshold fail.
 - For some providers (such as OKX), below-minimum deposits are not recoverable.

Internal transfers and rebalancing

You can transfer funds internally between supported account types:

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help C

/

Notes:

- Transfers are off-chain and do not incur network fees
- All internal transfers appear in the [Fireblocks Audit Log](#)
- Assets held in sub-accounts do not appear on the **My Assets** page
- Workspace Policies may require updates to allow certain transfer directions

Off-Exchange

[Off-Exchange](#) lets you manage collateral directly through Fireblocks while trading on supported centralized providers. Supported operations include:

- Adding and removing collateral through a collateral vault account
- Settling account balances with the provider
- Tracking assets, balances, available collateral, provider credit, and transactions

Security of provider API keys

Fireblocks encrypts provider API keys and stores them in a secure Fireblocks environment as part of its [secure cloud architecture](#).

Was this article helpful?

Yes

No

ON THIS PAGE

Connected account types

Connecting a provider account

View balances

Withdraw funds

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

Security of provider API keys



[fireblocks.com](#)

[Status](#)

[API Docs](#)

[Console](#)

[info@fireblocks.com](#)



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)