

Don't see what you're looking for? Log in for the full Help Center experience

EVM fees: Selecting transaction fees

Updated 1 year ago

Console

To select either estimated or exact fee levels:

1. Select **+ Transfer** or go to **Accounts > My Vault**.
2. Select your desired source vault account.
3. Select **Withdraw**  or **Deposit**  to initiate a new transfer.
4. In the New Transfer window, select the desired Asset.
5. Select the source account.
6. Select the destination account or address.
7. Enter the desired net or gross amount you wish to transfer.
8. Select one of the **Slow**, **Medium**, or **Fast** options per your desired fee level (parallel to Low, Medium & High), or select **Custom** and enter an exact fee.
9. Select **Create Transfer** to initiate the transfer.

API

The Fireblocks API lets you estimate blockchain and transaction fees using the following endpoints:

- [Estimate the required fee for an asset](#)
- [Estimate transaction fee](#)

Important

You must check whether you have enough funds in the source account to pay for the estimated fees before submitting the transaction. If you do not have enough funds, the transaction may fail and you will receive the [DROPPED_BY_BLOCKCHAIN error](#) in the Console, or the [Failed: Insufficient funds for fee status](#) via the API.

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

ON THIS PAGE

Console

API

Related Articles

-  [EVM fees: Fee rates](#)
-  [EVM fees: Fee validation](#)
-  [EVM fees: Fee behavior](#)
-  [EVM fees: Ethereum fee parameters](#)
-  [EVM fees: Overview](#)
-  [EVM fees: Net vs. gross fee selection](#)
-  [EVM fees: Adjusting network transaction fees](#)
-  [EVM fees: Minimum gas price limitations](#)
-  [EVM fees: Reviewing estimated and actual fees](#)



fireblocks.com

[Status](#)

[API Docs](#)

[Console](#)

info@fireblocks.com



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)