

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center 

HTX (formerly HUOBI) account

Updated 8 months ago

Configuring your HTX account

To configure your HTX account to connect to Fireblocks:

1. Refer to the [HTX.com API Documentation](#) to learn how to generate an Access key.
2. When prompted to do so, name your new Access Key "Fireblocks."
3. Copy and keep a record of both the Access Key and Secret Key. You will need them when adding this exchange to your workspace.
4. Make sure you enable the following permission settings:
 - **Withdraw.**
 - **Trade.**
5. Bind IP address or IP segment (optional): **52.76.208.129**

Configuring Fireblocks

1. **Accounts > Connected accounts.**
2. Select **+ Connect Account.**
3. Select **HTX**, select **Main Account**, and then complete the following fields:
 - a. **Name on Fireblocks:** Enter the name you want to give this exchange account on Fireblocks.
 - b. **Access Key:** Enter the Access key that you saved from HTX.
 - c. **Secret:** Enter the Secret key that you saved from HTX.
 - d. Select **Connect Account.**

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your HTX account appears on the Exchanges page along with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center



Enabling withdrawals from HTX

[Learn more about enabling exchange account withdrawals in Fireblocks.](#)

Enabling deposits to HTX

Make sure to generate a new address for each asset type on HTX to enable deposits from your vault account to HTX. See the [HTX documentation](#) for more information.

HTX requires a [manual deposit](#) for each asset type to generate a deposit address and initiate the connection with Fireblocks. All following transfers can be managed from your Fireblocks workspace. This is due to an HTX API limitation in identifying deposit addresses.

Was this article helpful?

Yes

No

ON THIS PAGE

Configuring your HTX account

Configuring Fireblocks

Enabling withdrawals from HTX

Enabling deposits to HTX

Related Articles



HTX (formerly Huobi) sub-account

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)