

Don't see what you're looking for? Log in for the full Help Center experience

Lightbit account

Updated 8 months ago

Configuring your Lightbit account

To configure your Lightbit account to connect to Fireblocks:

1. Refer to the [how to generate a Lightbit API Key](#) section below.
2. Copy and keep a record of both the API Key and API Secret. You will need them when adding this exchange to your workspace.
3. Under IP access restrictions, replace 0.0.0.0 with **52.76.208.129**

Configuring Fireblocks

1. In the Fireblocks Console, go to **Accounts > Connected accounts**.
2. Select **+ Connect Account**.
3. Select **Lightbit**, and then complete the following fields:
 - a. **Name on Fireblocks:** Enter the name you want to give this account on Fireblocks.
 - b. **API Key:** Enter the API key that you saved from Lightbit.
 - c. **API Secret:** Enter the Secret key that you saved from Lightbit.
4. Select **Connect Account**.

The [Admin Quorum](#) must approve the new account to make it available for new transfers from your workspace.

Your Lightbit account appears on the connected accounts page along with all managed assets and their balances. Following Admin Quorum approval, transfers are available from your vault accounts, whitelisted addresses, Fireblocks P2P Network connections, and other connected accounts to your Lightbit account.

Don't see what you're looking for? Log in for the full Help Center experience


 Fireblocks Fireblocks Help Center

/


[Learn more about enabling exchange account withdrawals in Fireblocks.](#)

How to generate a Lightbit API Key

1. Log in to your Lightbit account portal and go to **Menu > API Management**.



2. Select **Add New**.




3. Name your API "Fireblocks" and select **Submit**.


Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks

Fireblocks Help Center



4. The API key is created. Select **More** for additional details.



Was this article helpful?

Yes

No

ON THIS PAGE

Configuring your Lightbit account

Configuring Fireblocks

Enabling withdrawals from Lightbit

How to generate a Lightbit API Key

Related Articles

Don't see what you're looking for? Log in for the full Help Center experience



Gemini V2 Account