

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

Search the Help Center /

Setup for Gas Station 2.0

Updated 3 days ago

Fireblocks Gas Station 2.0 is an auto-fueling solution that gives you full control over gas management in your workspace. You can designate a single vault account as your Gas Station account and enable auto-fueling on individual vault accounts, removing the need to monitor balances or manually top up vault accounts.



To enable Gas Station 2.0 for your workspace, contact Fireblocks Support. Once enabled, auto-fueling triggers when you deposit tokens into a vault account that doesn't have enough gas to cover withdrawal fees. The triggering and refueling rules are the same as in Gas Station 1.0.

How to set up Gas Station 2.0

Step 1: Install an API Co-signer

Fireblocks recommends that you [install and configure an API Co-signer](#) to sign refueling transfers automatically on your behalf. Without one, a workspace user must sign each refueling operation manually using the Fireblocks mobile app.

Step 2: Configure your Policy rules

Don't see what you're looking for? Log in for the full Help Center experience

 Fireblocks Help Center

/

To prevent misconfigurations or unintended high-value top-ups, Fireblocks recommends adding a blocking rule before the auto-refueling rule. This blocking rule should enforce a maximum transfer value; for example, five times the maximum gas fee of the relevant asset.

Learn more about Policy rules:

- [Create a Policy rule](#)
- [Transactions not covered by your Policies](#)

Scope

Specify the extent of coverage for the rule.

Rule name

Gas station

Initiator

Auto-refuelling Service X

Source

Any vault account X

Destination

Any vault account X Any exchange X

☒ All addresses ☐ Whitelisted addresses ☐ One-time addresses only

Set an API Co-signer rule

Set a Policy rule that assigns your API Co-signer user as an approver, designated signer, or both for all refueling transactions.

Status	#	Name	Initiator	Source	Destination	Asset	Amount	Action	Signer
Added	01	Gas station signer	Auto-refueling	Any vault acc...	3 destinations	Any	\$0 - \$10,000 per transaction	Allow	API Co-Signer

For added security, Fireblocks recommends setting an explicit block rule to prevent the API Co-signer from initiating transactions.

Don't see what you're looking for? Log in for the full Help Center experience

Fireblocks Fireblocks Help Center



Station account.

2. Go to **Settings > General > Gas Station vault** and select the vault account you just created, or an existing one. **Gas Station** appears under the vault account name, and the account begins funding any vault accounts that have auto-fueling enabled.




Note

If you are migrating from Gas Station 1.0 to Gas Station 2.0 for the first time, Fireblocks automatically sweeps the remaining funds from your Gas Station 1.0 vault account into the newly designated Gas Station vault account.

Enable auto-fueling for vault accounts

You can enable or disable auto-fueling for vault accounts using the same procedures as in Gas Station 1.0. For instructions, see [Enable or disable Gas Station auto-fueling](#).

If you try to enable auto-fueling on a vault account before designating a Gas Station vault account, a modal prompts you to designate one.



Gas Station 2.0 webhooks

Gas Station 2.0 transactions have different webhook notification properties than Gas Station 1.0 transactions:

- The webhook's source type has changed from `GAS_STATION` to `VAULT_ACCOUNT`.

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



Gas Tank auto-fuel.

Was this article helpful?

Yes

No

Related Articles

-  Set Up the Gas Station
-  My Gas Station is configured properly but a transfer failed due to insufficient funds for fees
-  General troubleshooting for the Gas Station
-  About the Gas Station
-  Enable the Gas Station
-  Default Gas Station values
-  Configure Gas Station settings
-  About the Fireblocks Gasless Service
-  Enable or disable Gas Station auto-fueling
-  Gas Station Autoboot
-  View vault accounts with auto-fueling enabled
-  Fund the Gas Station
-  I received a deposit but the Gas Station didn't send any gas
-  View the Gas Station's current balance
-  Fireblocks Gas Station Transfers Source Type (November 2023)

Don't see what you're looking for? Log in for the full Help Center experience



Fireblocks Help Center



Fireblocks © 2026. All Rights Reserved. NMLS Registration Number: 2066055

[Privacy Policy](#)