Document diagnostics

The compiler keeps available Markdown content and valid diagrams visible when one diagram fails. Each failed block shows its source position and full message. Add `--diagnostics-summary` to include an overall error and warning count at the top of the document.

Failed Mermaid diagram

Diagram rendering error

`/home/evgeny-igumnov/blueprint4llm/examples/blueprint-diagnostics.md:11:1 · mermaid · diagram.render`

```
mermaid render failed: command failed with exit code 1: Error: Parse error
on line 3:
...art TB  Client -->
----------------------^
Expecting 'AMP', 'COLON', 'PIPE', 'TESTSTR', 'DOWN', 'DEFAULT', 'NUM',
'COMMA', 'NODE_STRING', 'BRKT', 'MINUS', 'MULT', 'UNICODE_TEXT', got 'EOF'
Parser.parseError (https://mermaid-cli-intercept.invalid/home/evgeny-
igumnov/blueprint4llm/node_modules/mermaid/dist/chunks/mermaid.esm/chunk-
LJKG65JO.mjs:1561:21)
Parser.parse (https://mermaid-cli-intercept.invalid/home/evgeny-
igumnov/blueprint4llm/node_modules/mermaid/dist/chunks/mermaid.esm/chunk-
LJKG65JO.mjs:1633:16)
    at #evaluate (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/cdp/ExecutionContext.js:402:19)
    at async ExecutionContext.evaluate (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/cdp/ExecutionContext.js:288:16)
    at async IsolatedWorld.evaluate (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/cdp/IsolatedWorld.js:104:16)
    at async CdpJSHandle.evaluate (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/api/JSHandle.js:154:20)
    at async CdpElementHandle.evaluate (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/api/ElementHandle.js:344:20)
    at async CdpElementHandle.$eval (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/api/ElementHandle.js:498:24)
    at async CdpFrame.$eval (file:///home/evgeny-
```

```
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/api/Frame.js:469:20)
    at async CdpPage.$eval (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/puppeteer-
core/lib/puppeteer/api/Page.js:462:20)
    at async renderMermaid (file:///home/evgeny-
igumnov/blueprint4llm/node_modules/@mermaid-js/mermaid-
cli/src/index.js:689:22)
    at fromText (https://mermaid-cli-intercept.invalid/home/evgeny-
igumnov/blueprint4llm/node_modules/mermaid/dist/mermaid.esm.mjs:1337:17)
```

The service continues after the first failure.

Valid draw.io diagram



This diagram and the surrounding text remain available.

Failed Balsamiq screen

Diagram rendering error

`/home/evgeny-igumnov/blueprint4llm/examples/blueprint-diagnostics.md:56:21 · balsamiq · diagram.render`

```
balsamiq render failed: Balsamiq control "submit" has an unsupported
typeID "UnknownControl"
```

The final paragraph remains available after both errors. Run `blueprint4llm` with `--check` to collect both diagnostics, or use `--report-json=diagnostics.json` to save their coordinates.