## AutomaticElectronicTollCollection

Generated by Doxygen 1.6.3

Tue Nov 9 22:53:59 2010

# **Contents**

1	File	Index		1
	1.1	File Li	st	1
2	File	Docum	entation	3
	2.1	src/AE	TC_GSMF.c File Reference	3
		2.1.1	Detailed Description	3
		2.1.2	LICENSE	4
		2.1.3	Function Documentation	4
			2.1.3.1 del_2s	4
			2.1.3.2 port_close	4
			2.1.3.3 port_config	4
			2.1.3.4 port_open	4
			2.1.3.5 write_data	4
	2.2	src/AE	TC_GSMS.c File Reference	6
		2.2.1	Detailed Description	6
		2.2.2	LICENSE	6
		2.2.3	Function Documentation	7
			2.2.3.1 del_2s	7
			2.2.3.2 main	7
			2.2.3.3 port_close	7
			2.2.3.4 port_config	7
			2.2.3.5 port_open	7
			2.2.3.6 write_data	7
	2.3	src/AE	TC lcd.c File Reference	8
		2.3.1	Detailed Description	ç
		2.3.2	LICENSE	ç
		2.3.3	Function Documentation	ç
		2.5.5		ć

ii CONTENTS

		2.3.3.2	lcd_init	9
		2.3.3.3	lcd_print	9
		2.3.3.4	lcd_set_4bit	10
		2.3.3.5	lcd_string	10
		2.3.3.6	lcd_wr_char	10
		2.3.3.7	lcd_wr_command	10
2.4	src/AE	TC_Robo	t.c File Reference	11
	2.4.1	Detailed	Description	12
	2.4.2	LICENS	E	12
	2.4.3	Function	Documentation	13
		2.4.3.1	ADC_Conversion	13
		2.4.3.2	adc_init	13
		2.4.3.3	init_devices	13
		2.4.3.4	main	13
		2.4.3.5	motion_set	14
		2.4.3.6	port_init	14
		2.4.3.7	print_sensor	14
		2.4.3.8	SIGNAL	14
		2.4.3.9	timer1_init	14
		2.4.3.10	timer5_init	15
		2.4.3.11	uart0_init	15
		2.4.3.12	velocity	15
	2.4.4	Variable	Documentation	16
		2.4.4.1	ADC_Value	16

# Chapter 1

# **File Index**

## 1.1 File List

Here is a list of all documented files with brief de
--

src/AETC_GSMF.c	. 3
src/AETC_GSMS.c	. (
src/AETC_lcd.c	. 8
src/AETC_Robot.c	. 11

2 File Index

## **Chapter 2**

## **File Documentation**

## 2.1 src/AETC\_GSMF.c File Reference

```
#include <stdio.h>
#include <string.h>
#include <malloc.h>
#include <unistd.h>
#include <fcntl.h>
#include <fcrtl.h>
#include <errno.h>
#include <termios.h>
#include <sys/time.h>
#include <sys/types.h>
```

## **Functions**

- int port\_open (void)
- void port\_config (int fd)
- void del\_2s (void)
- void write\_data (int fd, char \*c)
- void port\_close (int fd)
- int main (void)

## 2.1.1 Detailed Description

Program for serial communication between Owner and TollPlaza through GSM Module. Send Fail Message

## Author

Puskar Kothavade, Ashish Pardhi, Mugdha Nazare, IIT Bombay

#### **Date**

10/Oct/2010

#### Version

1.0

#### 2.1.2 LICENSE

Copyright (c) 2010. ERTS Lab IIT Bombay All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the copyright holders nor the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.

Source code can be used for academic purpose. For commercial use permission form the author needs to be taken.

#### 2.1.3 Function Documentation

#### 2.1.3.1 void del 2s (void)

Generate Delay of two seconds.

## 2.1.3.2 void port\_close (int fd)

Close port for reuse

#### **Parameters**

fd File Descriptor to access serial port

#### 2.1.3.3 void port\_config (int fd)

Configure port

#### **Parameters**

fd File Descriptor to access serial port

#### 2.1.3.4 int port\_open (void)

Open port for serial communication. display error messsage if unable to open.

#### 2.1.3.5 void write data (int fd, char \*c)

Send Message to register owner

## **Parameters**

fd File Descriptor to access serial port

\*c character pointer

## 2.2 src/AETC\_GSMS.c File Reference

```
#include <stdio.h>
#include <string.h>
#include <malloc.h>
#include <unistd.h>
#include <fcntl.h>
#include <fcrtl.h>
#include <errno.h>
#include <termios.h>
#include <sys/time.h>
#include <sys/types.h>
```

### **Functions**

- int port\_open (void)
- void port\_config (int fd)
- void del\_2s (void)
- void write\_data (int fd, char \*c)
- void port\_close (int fd)
- int main (void)

## 2.2.1 Detailed Description

Program for serial communication between Owner and TollPlaza through GSM Module. Send Success Message

#### Author

Puskar Kothavade, Ashish Pardhi, Mugdha Nazare, IIT Bombay

#### Date

10/Oct/2010

#### Version

1.0

#### 2.2.2 LICENSE

Copyright (c) 2010. ERTS Lab IIT Bombay All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the copyright holders nor the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.

Source code can be used for academic purpose. For commercial use permission form the author needs to be taken.

### 2.2.3 Function Documentation

#### 2.2.3.1 void del\_2s (void)

Generate Delay of two seconds.

## **2.2.3.2** int main (void)

< File Descriptor to access serial port

## 2.2.3.3 void port\_close (int fd)

Close port for reuse

#### **Parameters**

fd File Descriptor to access serial port

#### 2.2.3.4 void port\_config (int fd)

Configure port

## **Parameters**

fd File Descriptor to access serial port

## 2.2.3.5 int port\_open (void)

Open port for serial communication. display error messsage if unable to open.

## 2.2.3.6 void write\_data (int fd, char \*c)

Send Message to register owner

#### **Parameters**

fd File Descriptor to access serial port

\*c character pointer

## 2.3 src/AETC\_lcd.c File Reference

```
#include <avr/io.h>
#include <avr/delay.h>
#include <util/delay.h>
```

## **Defines**

```
• #define FCPU 11059200ul set the cpu frequency
```

• #define RS 0

set command input

• #define RW 1

writing to LCD

• #define EN 2

set Enable pin

- #define lcd\_port PORTC
- #define **sbit**(reg, bit) reg = (1 << bit)
- #define **cbit**(reg, bit) reg &=  $\sim$ (1<<bit)

## **Functions**

- void init\_ports ()
- void lcd\_reset\_4bit ()
- void lcd\_init ()
- void <a href="lcd\_wr\_command">lcd\_wr\_command</a> (unsigned char)
- void lcd\_wr\_char (char)
- void lcd\_home ()
- void <a href="led-cursor">lcd\_cursor</a> (char, char)
- void <a href="lcd\_print">lcd\_print</a> (char, char, unsigned int, int)
- void lcd\_string (char \*)
- void lcd\_set\_4bit ()

## **Variables**

- unsigned int temp
- unsigned int unit
- unsigned int tens
- unsigned int hundred
- unsigned int thousand
- unsigned int million
- int **i**

## 2.3.1 Detailed Description

Program for printing data on LCD.

#### Author

Puskar Kothavade, Ashish Pardhi, Mugdha Nazare, IIT Bombay

#### Date

10/Oct/2010

#### Version

1.0

#### 2.3.2 LICENSE

Copyright (c) 2010. ERTS Lab IIT Bombay All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the copyright holders nor the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.

Source code can be used for academic purpose. For commercial use permission form the author needs to be taken.

#### 2.3.3 Function Documentation

#### 2.3.3.1 void lcd\_cursor (char row, char column)

Position the LCD cursor at "row", "column".

#### **Parameters**

```
row no. of rowscolumn no. of columns
```

#### **2.3.3.2 void lcd\_init**()

Function to Initialize LCD

#### 2.3.3.3 void lcd\_print (char row, char coloumn, unsigned int value, int digits)

Function To Print Any input value upto the desired digit on LCD

## **2.3.3.4 void lcd\_set\_4bit** ()

Function to Reset LCD

## 2.3.3.5 void lcd\_string (char \* str)

Function to Print String on LCD

## 2.3.3.6 void lcd\_wr\_char (char *letter*)

Function to Write Data on LCD

## 2.3.3.7 void lcd\_wr\_command (unsigned char cmd)

Function to Write Command on LCD

## 2.4 src/AETC\_Robot.c File Reference

```
#include <avr/io.h>
#include <avr/interrupt.h>
#include <util/delay.h>
#include <avr/signal.h>
#include <math.h>
#include "AETC_lcd.c"
#include <avr/delay.h>
```

#### **Defines**

• #define FCPU 11059200ul

defined here to make sure that program works properly

#### **Functions**

- void port\_init ()
- void timer5\_init ()
- void velocity (unsigned char, unsigned char)
- void motors\_delay ()
- void timer1\_init ()
- unsigned char ADC\_Conversion (unsigned char)
- **ISR** (TIMER1\_OVF\_vect)
- void **lcd\_port\_config** (void)
- void adc\_pin\_config (void)
- void motion\_pin\_config (void)
- void adc\_init ()
- void print\_sensor (char row, char coloumn, unsigned char channel)
- void motion\_set (unsigned char Direction)
- void forward (void)
- void stop (void)
- void uart0\_init (void)
- void init\_devices (void)
- SIGNAL (SIG\_USART0\_RECV)
- int main ()

#### Variables

- unsigned char ADC\_Value
- unsigned char  $\mathbf{flag1} = 0$
- unsigned char  $\mathbf{flag2} = 0$
- unsigned char  $\mathbf{f} = 0$

stores flag values

```
• unsigned char Left_white_line = 0 
store left white line sensor value
```

- unsigned char Center\_white\_line = 0 store center white line sensor value
- unsigned char Right\_white\_line = 0 store right white line sensor value
- unsigned char Front\_Sharp\_Sensor = 0
   store front sensor value
- unsigned char **Front\_IR\_Sensor** = 0
- unsigned int **vehicle\_stop** = 0
- unsigned int LID\_Transmit = 0 store transmitted ID value
- unsigned char data store data
- float speed store speed
- unsigned char speed\_int
- unsigned char speed\_dec
- unsigned int **RegSpeed** = 150
- unsigned char **StartTheBot** = 0

## 2.4.1 Detailed Description

Program for speed calculation, white line follower and obstacle detection.

#### **Author**

Puskar Kothavade, Ashish Pardhi, Mugdha Nazare, IIT Bombay

#### **Date**

10/Oct/2010

#### Version

1.0

#### 2.4.2 LICENSE

Copyright (c) 2010. ERTS Lab IIT Bombay All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

Redistributions of source code must retain the above copyright notice, this list of conditions and the following disclaimer.

Redistributions in binary form must reproduce the above copyright notice, this list of conditions and the following disclaimer in the documentation and/or other materials provided with the distribution.

Neither the name of the copyright holders nor the names of contributors may be used to endorse or promote products derived from this software without specific prior written permission.

Source code can be used for academic purpose. For commercial use permission form the author needs to be taken.

#### 2.4.3 Function Documentation

#### **2.4.3.1** unsigned char ADC\_Conversion (unsigned char *Ch*)

- < Set start conversion bit
- < Wait for conversion to complete
- < clear ADIF (ADC Interrupt Flag) by writing 1 to it

#### **2.4.3.2 void adc\_init** ()

```
< MUX5 = 0
```

- < Vref=5V external --- ADLAR=1 --- MUX4:0 = 0000
- < ADEN=1 --- ADIE=1 --- ADPS2:0 = 1 1 0

### 2.4.3.3 void init\_devices (void)

- < Clears the global interrupts
- < initialise the ports

#### **2.4.3.4** int main (void)

#### Main Function

- < Getting data of Left WL Sensor
- < Getting data of Center WL Sensor
- < Getting data of Right WL Sensor
- < Getting data of Front Sharp sensor
- < Getting data of Front IR sensor
- < Prints value of White Line Sensor1
- < Prints Value of White Line Sensor2
- < Prints Value of White Line Sensor3
- < vehicle at first black patch
- < Timer 1 start witrh no prescaler
- < Getting data of Left WL Sensor
- < Getting data of Center WL Sensor

- < Getting data of Right WL Sensor
- < vehicle at second black patch
- < Timer 1 stop
- < vehicle at third black patch
- < Capturing photo in progress
- < photograph taken. Vehicle can go ahead now
- < Obstacle detection

#### **2.4.3.5** void motion\_set (unsigned char *Direction*)

Function used for setting motor's direction.

- < removing upper nibbel for the protection
- < reading the PORTA original status
- < making lower direction nibbel to 0
- < adding lower nibbel for forward command and restoring the PORTA status
- < executing the command

#### **2.4.3.6 void port\_init** ()

Functions prototype

## 2.4.3.7 void print\_sensor (char row, char coloumn, unsigned char channel)

Function To Print Sesor Values At Desired Row And Coloumn Location on LCD

## 2.4.3.8 SIGNAL (SIG\_USART0\_RECV)

Usart receiver ISR

- < making copy of data from UDR0 in data variable
- < To Regulate the speed
- < To transmit ID to Laptop
- < To transmit speed int value
- < To transmit speed value after decimal point
- < IF third black patch comes then transmit 1 otherwise 0.
- < Image capture process over. Vehicle can go ahead now.

## **2.4.3.9 void timer1\_init** ()

- < STOP
- < Timer register higher 8 bit to zero
- < Timer register lower 8 bit to zero

- < Output compare register higher 8 bits...not used in this case
- < Output compare register lower 8 bits.....not used in this case
- < Output compare register higher 8 bits...not used in this case
- < Output compare register lower 8 bits.....not used in this case
- < Output compare register higher 8 bits...not used in this case
- < Output compare register lower 8 bits.....not used in this case
- < Using channel A only, but not using output compare mode. WGM: normal mode COM10:1=00
- < No FOC
- < Timer overflow interrupt enabled
- < Setting I flag of status register to one to globally enable all interrupts

#### **2.4.3.10 void timer5\_init** ()

- < Stop
- < Counter higher 8-bit value to which OCR5xH value is compared with
- < Counter lower 8-bit value to which OCR5xH value is compared with
- < Output compare register high value for Left Motor
- < Output compare register low value for Left Motor
- < Output compare register high value for Right Motor
- < Output compare register low value for Right Motor
- < Output compare register high value for Motor C1
- < Output compare register low value for Motor C1
- $< \{COM5A1=1,COM5A0=0;COM5B1=1,COM5B0=0;COM5C1=1\ COM5C0=0\}\ For\ Overriding\ normal\ port\ functional it\ to\ OCRnA\ outputs.\ \{WGM51=0,WGM50=1\}\ Along\ With\ WGM52\ in\ TCCR5B\ for\ Selecting\ FAST\ PWM\ 8-bit\ Mode$
- < WGM12=1; CS12=0, CS11=1, CS10=1 (Prescaler=64)

## 2.4.3.11 void uart0\_init (void)

Function To Initialize UART0 desired baud rate: 9600 actual baud rate: 9600 (0.0%) char size: 8 bit parity: Disabled

- < disable while setting baud rate
- < set baud rate lo
- < set baud rate hi

## 2.4.3.12 void velocity (unsigned char *left\_motor*, unsigned char *right\_motor*)

Function for velocity control.

## 2.4.4 Variable Documentation

## 2.4.4.1 unsigned char ADC\_Value

Global Variables

# **Index**

ADC_Conversion	init_devices
AETC_Robot.c, 13	AETC_Robot.c, 13
adc_init	
AETC_Robot.c, 13	lcd_cursor
ADC_Value	AETC_lcd.c, 9
AETC_Robot.c, 16	lcd_init
AETC_GSMF.c	AETC_lcd.c, 9
del_2s, 4	lcd_print
port_close, 4	AETC_lcd.c, 9
port_config, 4	lcd_set_4bit
port_open, 4	AETC_lcd.c, 9
write_data, 4	lcd_string
AETC_GSMS.c	AETC_lcd.c, 10
	lcd_wr_char
main, 7	AETC_lcd.c, 10
port_close, 7	lcd_wr_command
port_config, 7	AETC_lcd.c, 10
port_open, 7	
write_data, 7	main
AETC_lcd.c	AETC_GSMS.c, 7
lcd_cursor, 9	AETC_Robot.c, 13
lcd_init, 9	motion_set
lcd_print, 9	AETC_Robot.c, 14
lcd_set_4bit, 9	
lcd_string, 10	port_close
lcd_wr_char, 10	AETC_GSMF.c, 4
lcd_wr_command, 10	AETC_GSMS.c, 7
AETC_Robot.c	port_config
ADC_Conversion, 13	AETC_GSMF.c, 4
	AETC_GSMS.c, 7
adc_init, 13	port_init
ADC_Value, 16	AETC_Robot.c, 14
init_devices, 13	port_open
main, 13	AETC_GSMF.c, 4
motion_set, 14	AETC_GSMS.c, 7
port_init, 14	print_sensor
print_sensor, 14	AETC_Robot.c, 14
SIGNAL, 14	
timer1_init, 14	SIGNAL
timer5_init, 15	AETC_Robot.c, 14
uart0_init, 15	src/AETC_GSMF.c, 3
velocity, 15	src/AETC_GSMS.c, 6
1-1 2-	src/AETC_lcd.c, 8
del_2s	src/AETC_Robot.c, 11
AETC_GSMF.c, 4	4:1 ::4
AETC_GSMS.c, 7	timer1_init

18 INDEX

AETC\_Robot.c, 14
timer5\_init
 AETC\_Robot.c, 15
uart0\_init
 AETC\_Robot.c, 15
velocity
 AETC\_Robot.c, 15
write\_data
 AETC\_GSMF.c, 4
 AETC\_GSMS.c, 7