#	Title	Steps	Expected Results	Actual Results	Frequency	Priority	Environment
1	Windows 10 - Sign In - "Sign In" screen opened again when click on "Back" button	1. Navigate to NDA 2. Click on "New!" category 3. Click on any product 4. Select any size (if required) 5. Click on "Add to Bag" button 6. Click on "Sign in"	Previous page (PDP) opened	"Sign In" screen opened again	Every Time	Medium	Win 10, Firefox, Chrome
2	Windows 10 - PDP - Reviews section overlaps Similar products carousel and footer	1. Navigate to NDA 2. Click on "Shoes" category 3. Click on any product 4. Click on "34 Reviews" 5. Click on "Left arrow" icon button 6. Click on "Right arrow" icon button 7. Scroll down to footer	"Similar products" carousel and footer displayed below reviews list	Reviews section overlaps Similar products carousel and footer	Every Time	Medium	Win 10, Firefox, Chrome
3	Windows 10 - PDP - Able to add products to cart over ship limit	1. Navigate to NDA 2. Click on "Shoes" category 3. Click on any product 4. Select any size 5. Enter 42 as product qty 6. Click on "Add to Cart" button 7. Enter 5 as product qty 8. Click on "Add to Cart" button 9. Click on "Add to Cart" button again	"Only 143 items available to ship" message appears, only 5 products added to cart	10 products added to cart (with 5 products ship limit)	Every Time	Medium	Win 10, Firefox, Chrome
4	Windows 10 - PDP - Nothing happens for first click on "Reviews"	1. Navigate to NDA 2. Click on "Shoes" category 3. Click on any product 4. Click on "34 Reviews"	Screen scrolled down to Reviews section	Nothing happens for first click on "Reviews"	Every Time	Low	Win 10, Firefox, Chrome
5	Premium - App crashes while close premium episodes category	1. Open the app 2. Open Premium menu 3. Tap on "More" option for any section 5. Tap on podcast (any) 6. Close podcast 7. Tap on "Back" button	Premium menu opened	App crashed	Every Time	High	Xiaomi Mi 6 - Android 9.0 (Pie)
6	Show Group - Unable to close show group if tap several times on Play button for premium episode	Preconditions: show group created, premium episode added to show group 1. Open the app 2. Tap on Shows tab 3. Open show group 4. Tap several times on Play button for premium episode 5. Close Premium window 6. Tap on Back button	Shows tab appears	Nothing happens when tap on "Back" button	Every Time	Low	Xiaomi Mi 6 - Android 9.0 (Pie)
7	Settings - Enter Code window is white color in dark color mode	1. Open the app 2. Tap on Settings button 3. Tap on account email 4. Tap on Password Recovery button 5. Close podcast 6. Tap on back button	Enter Code window is dark color	Enter Code window is white color	Every Time	Low	Xiaomi Mi 6 - Android 9.0 (Pie)
8	Queue - 2 more queue window appears after episode deletion	1. Open the app 2. Tap on Play button for any episode 3. Tap on Queue button 4. Tap on Edit 5. Tap on any episode 6. Tap on Remove from queue button 7. Close 2 queue windows	Episode deleted	2 more queue window appears	Every Time	Low	Xiaomi Mi 6 - Android 9.0 (Pie)