	1	2	3	4	5	6	7
ETAT	Closed	Connected	Wait	Sender Approved	Recipient approved	Writing Mail	Ready to Deliver
Connexion établie	Envoi "220 message de bienvenue", Etat 2	Impossible	Impossible	Impossible	Impossible	Impossible	Impossible
EHLO	Impossible	Envoi 250 OK, Etat 3	Envoi "503 Bad sequence of commands", Etat 3	Envoi "503 Bad sequence of commands", Etat 4	Envoi "503 Bad sequence of commands", Etat 5	Envoi "503 Bad sequence of commands", Etat 6	Envoi "503 Bad sequence of commands", Etat 7
MAIL FROM valide	Impossible	Envoi "503 Bad sequence of commands", Etat 2	Envoi "250 OK", Etat 4	Envoi "503 Bad sequence of commands", Etat 4	Envoi "503 Bad sequence of commands", Etat 5	Envoi "503 Bad sequence of commands", Etat 6	Envoi "250 OK", Etat 4
MAIL FROM invalide	Impossible	Envoi "503 Bad sequence of commands", Etat 2	Envoi "550 unknown user", Etat 3	Envoi "503 Bad sequence of commands", Etat 4	Envoi "503 Bad sequence of commands", Etat 5	Envoi "503 Bad sequence of commands", Etat 6	Envoi "503 Bad sequence of commands", Etat 7
RCPT TO invalide	Impossible	Envoi "503 Bad sequence of commands", Etat 2	Envoi "503 Bad sequence of commands", Etat 3	Envoi "550 unknown user", Etat 4	Envoi "550 unknown user", Etat 5	Envoi "503 Bad sequence of commands", Etat 6	Envoi "503 Bad sequence of commands", Etat 7
RCPT TO valide	Impossible	Envoi "503 Bad sequence of commands", Etat 2	Envoi "503 Bad sequence of commands", Etat 3	Envoi "250 OK", Etat 5	Envoi "250 OK", Etat 5	Envoi "503 Bad sequence of commands", Etat 6	Envoi "503 Bad sequence of commands", Etat 7
DATA	Impossible	Envoi "503 Bad sequence of commands", Etat 2	Envoi "503 Bad sequence of commands", Etat 3	Envoi "503 Bad sequence of commands", Etat 4	Envoi "354 Début des entrées du message", Etat 6	Envoi "503 Bad sequence of commands", Etat 6	Envoi "503 Bad sequence of commands", Etat 7
<crlf>.<crl F></crl </crlf>	Impossible	Envoi "503 Bad sequence of commands", Etat 2	Envoi "503 Bad sequence of commands", Etat 3	Envoi "503 Bad sequence of commands", Etat 4	Envoi "503 Bad sequence of commands", Etat 5	Envoi "250 OK", Etat 7	Envoi "503 Bad sequence of commands", Etat 7
RSET	Impossible	Envoi "503 Bad sequence of commands", Etat 2	Envoi "503 Bad sequence of commands", Etat 3	Envoi "250 OK", Etat 3	Envoi "250 OK", Etat 3	Envoi "250 OK", Etat 3	Envoi "250 OK", Etat 3
QUIT	Impossible	Envoi "221 Déconnexion", Etat 1	Envoi "221 Déconnexion", Etat 1	Envoi "221 Déconnexion", Etat 1	Envoi "221 Déconnexion", Etat 1	Envoi "221 Déconnexion", Etat 1	Envoi "221 Déconnexion", Etat 1