




GPIO I2C RCC							
Search Signals Search (Ctrl+F) Show only Modified Pins							
Pin N...	Signal on...	GPIO out...	GPIO mode	GPIO Pul...	Maximu...	User Label	Modified
PA0-WK...	n/a	Low	Output P...	No pull-u...	Low	FAN - Ou...	✓
PB0	n/a	n/a	Input mode	Pull-up	n/a	BTN1-Se...	✓
PB1	n/a	n/a	Input mode	Pull-up	n/a	BTN2-Se...	✓
PB12	n/a	n/a	Input mode	Pull-up	n/a	BTN3-Se...	✓

RCC Mode and Configuration

Mode

High Speed Clock (HSE)

Low Speed Clock (LSE)

☐ Master Clock Output

Configuration

☒ Parameter Settings
 ☒ User Constants
 ☒ NVIC Settings
 ☒ GPIO Settings

Configure the below parameters :

System Parameters

VDD voltage (V)	3.3 V
Prefetch Buffer	Enabled
Flash Latency(WS)	2 WS (3 CPU cycle)

RCC Mode and Configuration

Mode

Slave Mode

Trigger Source

☒ Internal Clock

Channel1

Channel2

Channel3

Channel4

Combined Channels

☐ XOR activation

☐ External Mode

Configuration

☒ Parameter Settings
 ☒ User Constants
 ☒ NVIC Settings
 ☒ DMA Settings

Configure the below parameters :

Counter Settings

Prescaler (PSC - 16 bits value)	7199
Counter Mode	Up
Counter Period (AutoReload Regis...	4999
Internal Clock Division (CKD)	No Division
auto-reload preload	Disable

Trigger Output (TRGO) Parameters

Master/Slave Mode (MSM bit)	Disable (Trigger input effect not delayed)
Trigger Event Selection	Reset (UG bit from TIMx_EGR)

Configuration

Reset Configuration

Parameter Settings

User Constants

NVIC Settings

DMA Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

I2C

I2C

Configuration

Reset Configuration

NVIC Settings

DMA Settings

GPIO Settings

Parameter Settings

User Constants

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
I2C2 event interrupt	☒	0	0
I2C2 error interrupt	☒	0	0

