UF_UGMGR_alt_id_status_e (view source)

Defined in: uf_ugmgr_types.h

Also known as:

• UF_UGMGR_alt_id_status_t

Overview

Alternate Id creation validation codes.

Data Members

UF_UGMGR_alt_id_valid

Alternate Id is valid

UF UGMGR_alt_id_invalid

Alternate Id is invalid, such as has invalid character, violates database pattern rules, etc.

UF_UGMGR_alt_id_modified

Alternate Id is valid but has been modified as output, due to naming rules, etc.

UF_UGMGR_alt_id_override

Alternate Id is valid but has been overwritten due to user exit, etc.

UF_UGMGR_object_type_e (view source)

Defined in: uf_ugmgr_types.h

Also known as:

• UF_UGMGR_object_type_t

Overview

PDM object types that can be accessed from NX Manager.

Data Members

UF_UGMGR_type_unknown

Unknown object type

UF_UGMGR_type_folder

Folder object type

UF_UGMGR_type_part

Part Item object type

UF_UGMGR_type_part_revision

Part Item Revision object type

UF_UGMGR_partno_status_e (view source)

Defined in: uf_ugmgr_types.h

Also known as:

UF_UGMGR_partno_status_t

Overview

Part Number creation validation codes.

Data Members

UF_UGMGR_partno_valid

Part Number is valid

UF_UGMGR_partno_invalid

Part Number is invalid, such as has invalid character, violates database pattern rules, etc.

UF_UGMGR_partno_modified

Part Number is valid but has been modified as output, due to naming rules, etc.

UF_UGMGR_partno_override

Part Number is valid but has been overwritten due to user exit, etc.

UF_UGMGR_rev_config_options_e (view source)

Defined in: uf_ugmgr_types.h

Also known as:

• UF_UGMGR_rev_config_options_t

Overview

Valid revision configuration options

Data Members

UF_UGMGR_configure_none

No revision option has been set

UF_UGMGR_configure_latest

The latest revision will be returned, even for configured input

UF_UGMGR_configure_by_rev_rule

Use the specified Revision Rule for configuration, even for configured input

UF_UGMGR_configure_all_revisions

All revisions will be returned, even for configured input