

File Window Help myST

Home STM32F103C8Tx Untitled - Pinout & Configuration GENERATE CODE

Pinout & Configuration Clock Configuration Project Manager Tools

Software Packs Pinout

RCC Mode and Configuration

Mode

High Speed Clock (HSE) Crystal/Ceramic Resonator

Low Speed Clock (LSE) Crystal/Ceramic Resonator

☐ Master Clock Output

Configuration

Reset Configuration

Parameter Settings User Constants NVIC Settings GPIO Settings

Configure the below parameters :

Search (Ctrl+F)

System Parameters

VDD voltage (V) 3.3 V

Prefetch Buffer Enabled

Flash Latency (WS) 0 WS (1 CPU cycle)

RCC Parameters

HSI Calibration Value 16

HSE Startup Timeout Value (ms) 100

LSF Startup Timeout Value (ms) 5000


Pinout view System view

STM32F103C8Tx LQFP48

Pinout diagram showing the STM32F103C8Tx LQFP48 package with pins labeled: VBAT, VDD, VSS, PC13, PC14, PC15, PD0, PD1, NRST, VSSA, VDDA, PA0, PA1, PA2, PA3, PA4, PA5, PA6, PA7, PB0, PB1, PB2, PB3, PB4, PB5, PB6, PB7, PB8, PB9, PA14, PA13, PA12, PA11, PA10, PA9, PA8, PB15, PB14, PB13, PB12, VSS, VDD.



Resolve Clock Issues



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

GPIO Mode and Configuration

Configuration

Group By Peripherals

GPIO

I2C

RCC

Search Signals

Search (Ctrl+F)

☐ Show only Modified Pins

Pin N...	Signal on...	GPIO out...	GPIO mode	GPIO Pul...	Maximu...	User Label	Modified
PA5	n/a	Low	Output P...	No pull-u...	Low	Motor_Ctrl	☒
PA6	n/a	n/a	Input mode	Pull-up	n/a	Button1	☒
PA7	n/a	n/a	Input mode	Pull-up	n/a	Button2	☒
PB0	n/a	n/a	Input mode	Pull-up	n/a	Button3	☒

PB0 Configuration :

GPIO mode

Input mode

GPIO Pull-up/Pull-down


Pull-up

User Label

Button3

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Slave Mode

Trigger Source

☒ Internal Clock

Channel1

Channel2

Channel3

Channel4

Combined Channels

☐ XOR activation

☐ One Pulse Mode

Configuration

Reset Configuration

☒ Parameter Settings ☒ User Constants ☒ NVIC Settings ☒ DMA Settings

Configure the below parameters :

Search (Ctrl+F)

Counter Settings

Prescaler (PSC - 16 bits value) 7199

Counter Mode Up

Counter Period (AutoReload Regi... 4999

Internal Clock Division (CKD) No Division


auto-reload preload Disable

Trigger Output (TRGO) Parameters

Master/Slave Mode (MSM bit) Disable (Trigger input effect not delayed)

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Slave Mode Disable

Trigger Source Disable

☒ Internal Clock

Channel1 Disable

Channel2 Disable

Channel3 Disable

Channel4 Disable

Combined Channels Disable

☐ XOR activation

☐ One Pulse Mode

Configuration


Reset Configuration

☒ Parameter Settings ☒ User Constants ☒ NVIC Settings ☒ DMA Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Project

Project Settings

Project Name

Home_Work

Project Location

C:\Users\عمرو\Documents\Lab\Assignment2

Browse

Application Structure

Advanced

☐ Do not generate the main()

Toolchain Folder Location

C:\Users\عمرو\Documents\Lab\Assignment2\Home_Work\

Toolchain / IDE

STM32CubeIDE

☒ Generate Under Root

Advanced Settings

Linker Settings

Minimum Heap Size

0x200

Minimum Stack Size

0x400

Thread-safe Settings

Cortex-M3NS

☐ Enable multi-threaded support

Thread-safe Locking Strategy

Default - Mapping suitable strategy depending on RTOS selection.



Mcu and Firmware Package

Mcu Reference

STM32F103C8Tx

Firmware Package Name and Version

STM32Cube_FW_F1_V1.8.5

☒ Use latest available version☒ Use Default Firmware Location

Firmware Relative Path

C:\Users\عمرو\STM32Cube\Repository\STM32Cube_FW_F1_V1.8.5

Browse

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Project

Project Settings

Project Name

Home_Work

Project Location

C:\Users\عمرو\Documents\Lab\Assignment2

Browse

Application Structure

Advanced

☐ Do not generate the main()

Toolchain Folder Location

C:\Users\عمرو\Documents\Lab\Assignment2\Home_Work\

Toolchain / IDE

ST

Code Generation



The Code is successfully generated under :

C:/Users/عمرو/Documents/Lab/Assignment2/Home_Work

Project language : C

Open Folder

Open Project

Close

Advanced Settings

Linker Settings

Minimum Heap Size

0x2

Minimum Stack Size

0x4

Thread-safe Settings

Cortex-M3NS

☐ Enable multi-threaded support

Thread-safe Locking Strategy

Default - Mapping suitable strategy depending on RTOS selection.

Mcu and Firmware Package

Mcu Reference

STM32F103C8Tx

Firmware Package Name and Version

STM32Cube FW_F1 V1.8.5

☒ Use latest available version☒ Use Default Firmware Location

Firmware Relative Path

C:/Users/عمرو/STM32Cube/Repository/STM32Cube_FW_F1_V1.8.5

Browse