NAME

ovn-detrace - convert "ovs-appetl ofproto/trace" output to combine OVN logical flow information.

SYNOPSIS

```
ovn-detrace < file
```

Common options:

DESCRIPTION

The **ovn-detrace** program reads **ovs-appctl ofproto/trace** output on stdin, looking for flow cookies, and expand each cookie with corresponding OVN logical flows. It expands logical flow further with the north-bound information e.g. the ACL that generated the logical flow, when relevant.

OPTIONS

- –h
- **--help** Prints a brief help message to the console.
- $-\mathbf{V}$
- --version

Prints version information to the console.

--ovnsb=server

The OVN Southbound DB remote to contact. If the OVN_SB_DB environment variable is set, its value is used as the default. Otherwise, the default is unix:@RUNDIR@/ovnsb_db.sock, but this default is unlikely to be useful outside of single-machine OVN test environments.

--ovnnb=server

The OVN Northbound DB remote to contact. If the OVN_NB_DB environment variable is set, its value is used as the default. Otherwise, the default is unix:@RUNDIR@/ovnnb_db.sock, but this default is unlikely to be useful outside of single-machine OVN test environments.

--ovs= Also decode flow information (like OVS ofport) from the flows by connecting to the OVS DB.

--ovsdb=server

The OVS DB remote to contact if **--ovs** is present. If the **OVS_RUNDIR** environment variable is set, its value is used as the default. Otherwise, the default is **unix:@RUNDIR@/db.sock**, but this default is unlikely to be useful outside of single-machine OVN test environments.

-p privkey.pem

--private-key=privkey.pem

Specifies a PEM file containing the private key used as **ovn-detrace**'s identity for outgoing SSL connections

-c cert.pem

--certificate=cert.pem

Specifies a PEM file containing a certificate that certifies the private key specified on $-\mathbf{p}$ or $--\mathbf{private-key}$ to be trustworthy. The certificate must be signed by the certificate authority (CA) that the peer in SSL connections will use to verify it.

−C cacert.pem

--ca-cert=cacert.pem

Specifies a PEM file containing the CA certificate that **ovn-detrace** should use to verify certificates presented to it by SSL peers. (This may be the same certificate that SSL peers use to verify the certificate specified on **-c** or **--certificate**, or it may be a different one, depending on the PKI design in use.)

SEE ALSO

 $\textbf{ovs-appctl}(8), \\ \textbf{ovn-sbctl}(8), \\ \textbf{ovn-nbctl}(8), \\ \textbf{ovn-trace}(8)$