

CSA1509-Cloud computing and Big Data Analytics

Name: SAMUVEL P

Reg.no: 192511280

EXP 12: Demonstrate virtualization by Installing Type-2 Hypervisor in your device, create and configure VM image with a Host Operating system (Either Windows/Linux).

Aim:


To demonstrate virtualization by installing Type-2 Hypervisor and to create and configure VM image with a Host Operating System .

Steps:


1. Download VMware software and install it as Type-2 Hypervisor.
2. Download Ubuntu or tiny os as ISO image file.
3. In VMware workstation → Create new VM
4. Do the basic configuration.
 - a. Change number of processors or memory size etc , if needed.
 - b. If extra hard disk is needed , double click on hard disk → add→additional hard disk.
5. Created a virtual Machine.
6. Launch the VM.

Implementation:


1. Download and open VMware software.



2.Create a new VM



Name it anything→click on next→Adjust the size of disk → change the option to first and then click on next.



Click on Finish to Launch .

3.VM is created

Ubuntu (7)

▶ Power on this virtual machine

🔗 Edit virtual machine settings

▼ Devices

Memory	4 GB
Processors	2
Hard Disk (SCSI)	10 GB
CD/DVD (SATA)	Auto detect
Network Adapter	NAT
USB Controller	Present
Sound Card	Auto detect
Printer	Present
Display	Auto detect

▼ Description

Type here to enter a description of this virtual machine.



▼ Virtual Machine Details

State:

Powered off

Configuration file:

C:\Users\G POOJITHA\Documents\Virtual Machines\Ubuntu (7)\Ubuntu (7).vmx

Hardware compatibility:

Workstation 17.x virtual machine

Primary IP address:

Network information is not available

4. Double-click on each and Change the memory size , number of hard disks , number of processors if needed.

HardwareOptions

Device	Summary
Memory	4 GB
Processors	2
Hard Disk (SCSI)	10 GB
CD/DVD (SATA)	Auto detect
Network Adapter	NAT
USB Controller	Present
Sound Card	Auto detect
Printer	Present
Display	Auto detect

Memory

Specify the amount of memory allocated to this virtual machine. The memory size must be a multiple of 4 MB.

Memory for this virtual machine: 4096 MB

128 GB -

64 GB -

32 GB -

16 GB -

8 GB -

4 GB -

2 GB -

1 GB -

512 MB -

256 MB -

128 MB -

64 MB -

32 MB -

16 MB -

8 MB -

4 MB -

Maximum recommended memory

(Memory swapping may occur beyond this size.)

13.2 GB

Recommended memory

4 GB

Guest OS recommended minimum

2 GB

5. VM is created and configured.

Ubuntu (7)

▶ Power on this virtual machine

🔗 Edit virtual machine settings

▼ Devices

Memory	7.8 GB
Processors	2
Hard Disk (SCSI)	10 GB
CD/DVD (SATA)	Auto detect
Network Adapter	NAT
USB Controller	Present
Sound Card	Auto detect
Printer	Present
Display	Auto detect

▼ Description

Type here to enter a description of this virtual machine.

▼ Virtual Machine Details

State:

Powered off

Configuration file:

C:\Users\G POOJITHA\Documents\Virtual Machines\Ubuntu (7)\Ubuntu (7).vmx

Hardware compatibility:

Workstation 17.x virtual machine

Primary IP address:

Network information is not available