CPPC 18/L

COMPUTER NETWORK & SECURITY

ACTIVITY No.6

HTTP

Submitted by:

LOGATOC, APRIL FOILA JOY M.

BS CpE 3B

Submitted to:

ENGR. JAN ERROL MAMPUSTI

Subject Professor

I. Objectives

- To enable the HTTP service on a server.
- To access a webpage through a web browser.
- To understand how HTTP allows web communication in a network.
- To verify if a PC can successfully open a webpage hosted by the server.

II. Materials

- Cisco Packet Tracer
- 1 Server
- 1 Switch
- 1–2 PCs
- Laptop
- Copper Straight-Through cables

III. Procedures

1. Build the Network Topology

- Open Cisco Packet Tracer.
- Add the required devices in the workspace:
  - 1 Server
  - 1 Switch
  - 1–2 PCs
- Connect the devices using Copper Straight-Through cables:
  - PC to Switch
  - Server to Switch
- Make sure that all connections are properly linked and active.

2. Configure the Server IP Address

- Click the Server.
- Go to Desktop.
- Open IP Configuration.
- Set the server with the following IP configuration:
    - IP Address: 192.168.1.1
    - Subnet Mask: 255.255.255.0
- This IP address will be used by the PCs to access the web server.

3. Enable HTTP Service

- Click the Server.
- Go to the Services tab.
- Select HTTP.
- Turn the HTTP service ON.
- This allows the server to host and provide a webpage that can be accessed by the client PCs.

4. Configure the PC IP Address

- Click the PC.
- Go to Desktop.
- Open IP Configuration.
- Choose Static IP configuration.
- Set the following IP address for PC0:
    - IP Address: 192.168.1.11
    - Subnet Mask: 255.255.255.0
- Set the following IP address for PC1:

- IP Address: 192.168.1.12
- Subnet Mask: 255.255.255.0

- Make sure that the PCs are in the same network as the server.

5. Access the Website

- Click the PC.
- Go to Desktop.
- Open Web Browser.
- In the URL bar, type:
  - http://192.168.1.1
- Click Go.
- The webpage should appear if the HTTP service and IP settings are configured correctly.

IV. Conclusion

The activity showed how to configure a server to host a webpage using HTTP in Cisco Packet Tracer. By enabling the HTTP service on the server and accessing its IP address through the PC's web browser, the webpage was displayed successfully. This proves that HTTP allows client devices to access web content over a network and confirms that the server is working properly as a web host.

V. Documentation




Server0
Physical
Config
Services
Desktop
Programming
Attributes
IP Configuration
X
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.1
Subnet Mask
255.255.255.0
Default Gateway
0.0.0.0
DNS Server
0.0.0.0


Server0
Physical
Config
Services
Desktop
Programming
Attributes
SERVICES
HTTP
DHCP
DHCPv6
TFTP
DNS
SYSLOG
AAA
NTP
EMAIL
FTP
IoT
VM Management
Radius EAP
PRP
HTTP
HTTP
On
Off
HTTPS
On
Off
File Manager
File Name
Edit
Delete
1 copyrights.html (edit) (delete)
2 cscoptlogo177x111.jpg (delete)
3 helloworld.html (edit) (delete)
4 image.html (edit) (delete)
5 index.html (edit) (delete)


PC0
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.11
Subnet Mask
255.255.255.0
Default Gateway
0.0.0.0
DNS Server
0.0.0.0


PC1
Physical
Config
Desktop
Programming
Attributes
IP Configuration
X
Interface
FastEthernet0
IP Configuration
DHCP
Static
IPv4 Address
192.168.1.12
Subnet Mask
255.255.255.0
Default Gateway
0.0.0.0
DNS Server
0.0.0.0


PC0
Physical
Config
Desktop
Programming
Attributes
Web Browser
X
<
>
URL
http://192.168.1.1
Go
Stop
Cisco Packet Tracer
Welcome to Cisco Packet Tracer. Opening doors to new opportunities. Mind Wide Open.
Quick Links:
A small page
Copyrights
Image page
Image


PC1
Physical
Config
Desktop
Programming
Attributes
Web Browser
X
<
>
URL
http://192.168.1.1/index.html
Go
Stop
Cisco Packet Tracer
Welcome to Cisco Packet Tracer. Opening doors to new opportunities. Mind Wide Open.
Quick Links:
A small page
Copyrights
Image page
Image