# Waves GTR Amp User Guide













### **TABLE OF CONTENTS**

CHAPTER 1 – INTRODUCTION	. 3
1.1 Welcome	. 3
CHAPTER 2 – QUICKSTART GUIDE	. 5
CHAPTER 3 – CONTROLS AND INTERFACE	. 6
3.1 AMP TYPES Clean. Drive High Gain. Neil Citron. Bass 3.2 AMP CONTROLS 3.3 CABINETS AND MICROPHONES Cabinets. Bass Cabinets Microphones 3.4 CABINET AND MICROPHONE CONTROLS 3.5 AMP COMPONENTS.	. 6 . 7 . 8 . 9 10 11 12 13 14 16
4.1 THE WAVESYSTEM TOOLBAR  Toolbar Functions  4.2 PRESET HANDLING  Preset Types  Loading Presets and Setups  Saving Presets and Setups  Deleting Presets  A/B Comparison and Copying  4.3 INTERFACE CONTROLS  Toggle Buttons  Value Window Buttons  Sliders  Hover Box  Multiple Selection of Controls  TAB Functions	20 20 22 22 23 23 24 24 25 25 25
APPENDIX	26

## Chapter 1 – Introduction

### 1.1 Welcome

Thank you for choosing Waves! In order to get the most out of your Waves processor, please take the time to read through this manual.

In conjunction, we also suggest that you become familiar with <a href="https://www.wavesupport.net">www.wavesupport.net</a>. There you will find an extensive Answer Base, the latest Tech Specs, detailed Installation guides, new Software Updates, and current information on Authorization and Registration.

By signing up at <a href="www.wavesupport.net">www.wavesupport.net</a>, you will receive personalized information on your registered products, reminders when updates are available, and information on your authorization status.

### 1.2 Product Overview

Waves Amp is a primary component of GTR, which features an exceptional selection of virtual amplifiers, cabinets, and microphones. While GTR was designed to be used with electric guitar, it's also a powerful set of tools for processing and re-amping drum or vocal tracks.

Each amp has two main sections:

- **Amp Type** With controls for amp selection and tone adjustment.
- Cabinet & Mic With controls for cabinet selection, microphone selection, and microphone position.

### 1.3 Components

WaveShell technology enables us to split Waves processors into smaller plug-ins, which we call **components**. Having a choice of components for a particular processor gives you the flexibility to choose the configuration best suited to your material.

Waves GTR Amp includes Mono, Mono Dual Cabinet, Mono-to-Stereo, and Stereo configurations. The Mono Dual Cab, Mono-to-Stereo, and Stereo components can each accommodate one amplifier with two cabinets. In Mono-to-Stereo and Stereo configurations, the output of each cabinet can be panned independently.

## Chapter 2 – Quickstart Guide

- When you open the Waves Amp plug-in on a track insert, it's ready to go with the default Clean amp.
- Use the Drive control to crank up the gain for more intensity without changing your output volume.
- For a more distorted tone, choose an amp with more Drive from the Amp Type menu. Amps are sorted in an escalating gain order.
- Once you've selected your amplifier, open up a post-amp PedalBoard. Reverb, Vibrolo, Delay, EQ, and Compression all work well as post-amp effects.
- Here's an example of a possible full setup:
   Stomp 6 Mono-to-Stereo PedalBoard with its default preset,
   followed by a Stereo Amp, followed by a Stomp 2 Stereo
   PedalBoard with Vibrolo and Spring Reverb Stomps.

## Chapter 3 – Controls and Interface

### 3.1 Amp Types

Select the amp model using the Amp Types menu. Amps are sorted into groups by application or drive rating. Each group has a unique skin.

**CLEAN** amps are displayed with a golden panel and tweed skin.



- Direct Full-frequency, transparent tone
- Clean Based on a 1959 tweed Fender® Bassman®.
- Warm Based on a boutique amp from Paul Reed Smith's private collection.
- Punchy Based on a 100W Marshall® head
- Sweet Based on a 1968 Gibson® Skylark

**DRIVE** amps are displayed with a blue panel and gold threaded cloth skin.




- Cream Based on a 1966 Ampeg® Gemini II
- Edgy Based on a 1980 Vox® AC-30 TB-2
- **Drive** Based on a 1964 blackface Fender® Super Reverb®
- Overdrive Based on a 1980 Marshall® JMP
- Scream Based on a custom amp from Paul Reed Smith's private collection

**HIGH GAIN** amps are displayed with a red wine panel and treadmill skin.



- **Crunch** Based on a custom Garcia<sup>™</sup> from Paul Reed Smith's personal collection
- Crush Based on a modified Marshall® MK2 50W stack head
- **Scorch** Based on a boutique amp from Paul Reed Smith's private collection
- Inferno A virtual model with super-high distortion and extremely fast cleanup
- Monster Based on a Marshall® 100W head
- Hot Based on a Koch® Combo
- Modern Based on a Mesa® Dual Rectifier® Solo head
- Shredder Based on a Marshall® JMP1 preamp
- Supernatural Based on a boutique amp from Paul Reed Smith's private collection





- Legatron Clean Based on a customized Carvin® Legacy
- Legatron Crunch Based on a customized Carvin® Legacy
- Thermitron Clean Based on an Ibanez® TN120 Thermion
- Thermitron Crunch Based on an Ibanez® TN120 Thermion
- Plexitron Lite Based on a modified 60s 100W Marshall® Plexi
- Plexitron Crunch Based on a modified 60s 100W Marshall® Plexi

**BASS** amps are displayed with a silver panel and grill skin.



- **Directube** Based on a Countryman® DI into a V72 preamp
- Activator Based on a Sadowsky® preamp
- SolidState Based on a Hartke® 3500
- Mo'Town Based on a fliptop Ampeg® B15-N tube amplifier
- SuperTube Based on the Ampeg® SVT
- Thunder Based on a David Eden® World Tour 800
- OverBass Based on a Mesa/Boogie® 400+

### 3.2 Amp Controls

All Amps feature Drive, Bass, Mid, Treble, and Presence controls, whose response curves are tailored to complement the specific amp type.





**Drive** controls the drive level range of +12dB to -12dBfs, with a default of 0dB.

**Range**: 0 to 10

Default: 5

**Bass** controls low frequency equalization cut/boost.

**Range**: -5 to +5

Default: 0

**MID** controls midrange frequency equalization cut/boost.

**Range**: -5 to +5

Default: 0

**TREBLE** controls high frequency equalization cut/boost.

Range: -5 to +5

Default: 0

PRESENCE controls high frequency equalization cut/boost.

**Range**: -5 to +5

Default: 0

**DIRECT** when Bass Amp types are selected the Presence control is replaced by the Direct control, which controls the amount of direct mixed with the processed signal.

**Range**: 0 to 10

Default: 0



**AMP** controls Amp activation/bypass. When set to Bypass, input is routed directly to the cabinet and mic.

Range: On/Bypass

Default: On

**TYPE** controls Amp selection. **Range**: Direct to OverBass

**Default**: Clean

### 3.3 Cabinets and Microphones

Cabinets and microphones are selected by using the appropriate menu selector.

Toggle through them by clicking on the text bar, or click on the arrow to the right of the text bar to display a drop-down list.

Each cabinet offers a choice of 6 microphones, which may be positioned either on or off axis.

Please note: "No Cabinet" uses neither a cabinet nor microphone, and is the default choice for the Direct Amp.



#### **CABINETS**

Select from 22 speaker cabinets.

- 4 x 12" Standard Based on a Marshall® 1960a
- 4 x 12" Vintage Based on Marshall® 1960ax with Celestion® G12 Greenbacks

- 4 x 12" Britt Based on an Orange® PPC412 with Celestion® Vintage30s
- 4 x 12" Inferno Based on a virtual cabinet
- 2 x 12" ClosedBack Based on a Marshall® 1936 cabinet with Celestion® G12 Greenbacks
- 2 x 12" OpenBack Based on a Vox® AC-30 Celestion® Alnico
- 4 x 10" OpenBack Based on a Fender® Super Reverb® Blackface 1968 with CTS alnico magnet speakers
- 12" OpenBack Based on a Mesa/Boogie® Mark IV with an Electro-Voice® speaker
- 15" ClosedBack Based on a 1960's Fender® Showman cabinet
- Acme 12" Custom Based on a custom cabinet by Ted Jensen of Sterling Sound
- Acme 2 x 10" Cabinet Based on a 1962 Vox® cabinet
- Acme 8" OpenBack Based on a 1968 Gibson® Skylark
- Acme 4 x 12" Cab Based on a 1970's Hiwatt® cabinet
- Acme 12" OpenBack Based on a mid '60s Ampeg Gemini cabinet
- Acme 2 x 10" OpenBack Based on a 1965 Fender® Vibrolux® Reverb Blackface cabinet
- Acme Case Speaker Based on a late '60s Silvertone® case with built-in speaker

#### BASS CABINETS

- Bass 8 x 10" Pro Based on an Ampeg® SVT810AV
- Bass 6 x 10" Based on an Ampeg® SVT610HL
- Bass 15" Based on a late '60s Fender® Bassman®
- Bass 15" Fliptop Based on an Ampeg® B15N
- Bass E15 15" + (4 x 10") Based on David Eden® cabinets
- Bass M1516 10" + 15" + (2 x 6") Based on a Mesa/Boogie® 1516

#### **MICROPHONES**

Select from different microphones, recorded in different positions.

- **Dyn 409** Based on a Sennheiser® Echolette 409 (dynamic)
- Dyn 421 Based on a Sennheiser® MD-421 II (dynamic)
- **Dyn 57** Based on a Shure® SM57 (dynamic)
- **Ribb 84** Based on a AEA® R84 (ribbon)
- **Ribb 44** Based on a RCA® 44 (ribbon)

- **Dyn RE20** Based on a Electro-Voice® RE20 (dynamic)
- Cond VM1 Based on a Brauner VM1® (condenser)

#### Bass Mics

- Coil 88 Based on a Beyer® M88 (dynamic moving coil)
- **Dyn** Based on a RE20 Electro Voice® RE20 (dynamic)
- **Dyn 57** Based on a Shure® SM57 (dynamic)
- Cond 87 Based on a Neumann® U87 (condenser)
- Cond GR Based on a Manley® Gold Reference (condenser)
- Ribb 122 Based on a Royer® 122 (ribbon)

### 3.4 Cabinet and Microphone Controls



Vol controls Cab/Mic volume.

Range: 0 to 10 Default: 5

**Phase** controls Cab/Mic polarity (DualCabinet only).

Range: Up/Down (Up = natural phase, Down = inverted phase)

Default: Up

**Pan** controls cabinet positions within the stereo field. (Mono-to-Stereo and Stereo amps only).

**Range**: -100 to +100

Default: 0

**DELAY** controls the amount of delay applied to the cabinet's output.

**Range**: 0 – 100

Default: 0



MASTER VOLUME controls overall output gain. Output meter includes red light clip indicator.


Range: 0 to 10

Default: 5

### 3.5 Amp Components

#### Mono Amp





The Mono Amp is the least CPU-intensive of the Amp components. It inputs and outputs a Mono signal, running the output through a single Amp module and then into a single cabinet/microphone filter.

#### Mono DualCab




The Mono DualCab amp is similar to the Mono amp in that it inputs and outputs a Mono signal. The DualCab configuration lets you play the Amp's sound through two separate cabinets. This allows for combinations such as loading the same cabinet with different microphones or using two different cabinets with the same mic.

The outputs of the two sources are then mixed together to a single output. Each cabinet has a phase switch and a volume control.

Please note: Selecting the same cabinet and microphone for both cabinets will result in a normal Mono single cabinet sound. In this case, inverting the phase of one of the two cabinets will result in a silent output.

#### Mono-to-Stereo and Stereo





The Mono-to-Stereo and Stereo Amps share the same controls and graphic user interface, but their input and processing specifications are different.

Mono-to-Stereo is very similar to the Mono DualCab component, but outputs a Stereo signal. Rather than adding each cabinet's output to a single path you can pan them to create a Stereo image from the Mono input.

The Stereo Amp component is actually a dual-Mono configuration which takes a Stereo input and outputs Stereo. The Left input goes through the Amp type to cabinet 1 and the Right input goes to cabinet 2. The Pan control can be used to limit the Stereo image width, collapse the Stereo input to a Mono output, or swap the channel outputs by hard panning them in opposite directions.

### 3.6 HD (High Definition) Option



The HD Option control is located at the top right of the plug-in's toolbar. It is off by default.

When running GTR at 44.1 or 48kHz, you have the option of doubling the internal amplifier sampling rate. HD offers fewer aliasing artifacts, and is especially useful for High Gain models.

Please note: Engaging the HD option will increase your CPU load.

When running at HD sample rates 88.2 or 96kHz the HD option is not available.

#### **Important Note for Pro Tools TDM Users**

The HD option as described above applies only to the GTR Amp RTAS plug-in. Under TDM, the GTR Amp with HD is offered as a separate mono-only plug-in.

## Chapter 4 - The WaveSystem

### 4.1 The WaveSystem Toolbar



All Waves processors feature the WaveSystem toolbar which takes care of most administrative functions you will encounter while working with your Waves software. The features of the WaveSystem toolbar are the same on practically all Waves processors, so familiarity with its features will be helpful whichever processor you are using.

#### **TOOLBAR FUNCTIONS**

**Undo** Undoes the last 32 actions. GTR supports multiple undo

levels.

**Redo** Redoes the last 32 undone actions.

**Setup A/B** Toggles between two presets. This is useful for close

comparison of different parameter settings

Copy A->B Copies the current settings to the second preset register

**Load** Recalls presets from file

**Save** Saves presets in the Waves file formats

? Opens the manual for the processor you are using

### 4.2 Preset Handling

#### PRESET TYPES

**Factory Presets** are permanent presets in the Load menu. Factory presets cannot be over-written or deleted. When applicable, different component plug-ins may have different factory presets.

**User Presets** are your favorite settings of the plug-in saved as a preset in the Load menu, under 'User Presets'. User Presets can be overwritten and deleted.

**Setup Files** may contain more than one preset. For example, a single file can contain all the presets for a session. When you open a Setup

File, all its setups become part of your Load pop-up menu for fast access. This can be particularly useful with multiple instances of a plug-in in a single session. By saving all the settings you create into a single Setup File, they can all be quickly available for every instance of that plug-in.

#### LOADING PRESETS AND SETUPS



Click-and-hold on the Load button to see the Load pop-up menu. The menu is divided into four sections. If a section is not currently available it will not appear in the Load pop-up menu.

**Open Preset File...** Select to open any setup or preset file,

whether from the Library or your own creations.

'Filename.xps': Displays any currently loaded Setup File and its

presets.

**Factory Presets:** Displays the default Factory Presets. **User Presets:** Displays any loaded User Presets.

#### SAVING PRESETS AND SETUPS



Click-and-hold on the Save button to see the Save pop-up menu. Four options are available. If an option is not currently available it will be grayed out and inaccessible.

**Save to New File...** Select this to start a new Setup file.

There are two prompts - first for the setup filename, then for the preset name. You must provide a name for both the setup file and the preset. Click OK (ENTER) to complete the save. It is a good idea to create a folder in which to

save several setup files for a project.

Save 'File Name' - "Preset Name" Overwrites the settings of the

loaded preset (whether a User Preset or a preset from a Setup File) with the current settings. If a Setup File is currently loaded, the name of the Setup

File is displayed followed by the name of the preset itself. If a User Preset is

loaded, its name is displayed.

Save to 'File Name' As... Saves the current settings as a new

preset into the Setup file that is open (if one is not open, the option is grayed

out). You will be prompted to give the

preset a name.

Put into Preset Menu As... Save the current settings into a User Preset that will always be in your Load

menu (until deleted). You will be prompted to give this preset a name. User Presets are stored in the plug-in's

preference file.

#### **DELETING PRESETS**

You may delete User Presets and presets within a Setup File. Factory Presets and Setup Library files cannot be deleted or overwritten.

- 1. Hold the Command (Mac)/Control (PC) key down.
- 2. Click-and-hold the Load button to see the pop-up menu.
- 3. While still holding the Command/Control key, select the preset or setup to delete.
- 4. A confirmation box will appear, allowing you to cancel or 'OK' the deletion.

#### A/B COMPARISON AND COPYING

The Setup A/Setup B button may be clicked to compare two settings. If you load a preset in the Setup B position, this will not affect the preset loaded into the Setup A position, and vice-versa.

If you want to slightly modify the settings in Setup A, you can copy them to Setup B by clicking on the Copy to B button, then alter Setup A and compare with the original Setup B.

The name of the current setup will be shown in the title bar (on platforms which support it), and will switch as you change from Setup A to Setup B.

Note: an asterisk will be added to the preset name when a change is made to the preset.

### 4.3 Interface Controls

Controls can be in one of three states:

- Not Selected where the control is not the target of any user entry
- Selected where the control is the target of mouse control entry only
- Selected and Active where the control is the target for both mouse and keyboard entry

#### **TOGGLE BUTTONS**

Toggle buttons display the state of a control, and allow switching between two or more states. **Single-click** to change the control's state. Some toggle buttons have a text display which updates with the current setting, and others (bypass, solo, or monitoring toggles) illuminate when the control is active.

Some processors have **link buttons** between a pair of toggle buttons, allowing click-and-drag adjustment while retaining the offset between the controls.

#### **VALUE WINDOW BUTTONS**

Value windows display the value of a control and allow click-and-drag adjustment, or direct control via the keyboard.

- **Using the mouse**, click-and-drag on the value window to adjust. Some value windows support left/right, some up/down (as you hover over a button, arrows will appear to let you know which direction of movement that button supports).
- Using the arrow keys, click once with mouse to select the button, and then use up/down left/right (depending on the direction supported by that button) to move in the smallest incremental steps across the button's range (holding down the arrow keys will move faster through the range).
- Using key entry, double click on the button to open the value window, and directly enter the value from your keyboard. If you enter an out of range number, the button stays selected but remains at the current setting (system beeps? If system sounds are on?)

Some processors have **link buttons** between a pair of value windows, allowing click-and-drag adjustment while retaining the offset between the controls.

#### **S**LIDERS

Click on the slider itself or anywhere within the sliders track. The numerical value of the slider settings is displayed in a hover window above the slider path.

#### **HOVER BOX**

Hovering boxes will appear and display the control value when hovering with the mouse over the control.

#### MULTIPLE SELECTION OF CONTROLS

One of the most powerful features of the WaveSystem is the ability to select and adjust many controls at the same time. Using the mouse, simply drag-select the desired group of button or graphic controls by clicking and holding at a point outside the controls and forming a rectangle to include the controls you wish to adjust. Alternatively, you can hold down Shift while clicking the mouse on any control you wish to link. This second method is useful when you want to select two (or more) controls that are separated on the GUI by other controls you do not wish to select.

#### **TAB FUNCTIONS**

TAB moves the 'selected' status to the next control, with shift-TAB moving in the reverse direction.

Additionally, the Mac has an option-TAB function for 'down' movement and shift-option-TAB for 'up' movement where applicable.

If you have several Value Window Buttons selected, TAB functions will take you through the selected controls only.

## **Appendix**

All product names and trademarks are the property of their respective owners, which are in no way associated or affiliated with Waves. Product names are used solely for the purpose of identifying the specific products that were studied during Waves' sound modeling process and for describing certain types of tones produced with Waves' proprietary algorithms. Use of these names does not imply any cooperation or endorsement.

Gibson® is a trademark of Gibson Guitar Corp.

Mesa/Boogie® and Rectifier are trademarks of Mesa/Boogie Ltd.

Silvertone® is a trademark of Samick Music Corporation

Marshall® is a registered trademark of Marshall Amplification Plc.

Fender®, Super Reverb®, and Bassman® are registered trademarks of Fender Musical Instruments Corporation.

Ampeg® is a registered trademark of St. Louis Music, Inc.

Koch® is a registered trademark of Koch Guitar Electronics

Vox® is a registered trademark of Korg Europe Ltd.

Sadowsky® is a registered trademark of Sadowsky Guitars Ltd.

Hartke® is registered trademark of Samson Technologies Corp

David Eden® is a registered trademark of Eden Electronics

Countryman® is a registered trademark of Countryman Associates Inc.

Neumann® is a registered trademark of Georg Neumann GmbH

Shure® is a registered trademark of Shure Incorporated

Brauner® is a registered trademark of Brauner Microphones

AKG® is a registered trademark of AKG Acoustics, Austria, A Harman International Company

Sennheiser® is a registered trademark of Sennheiser Electronic GmbH & Co. KG

RCA® is a registered trademark of Thomson SA

Celestion® is a registered trademark of KH Technology Corporation

Hiwatt® is a registered trademark of Fernandes Company Ltd.

Royer® is a registered trademark of Royer Labs