

FIRST INSTALLATION

For a first installation of **PolSARpro v6.0.4** (**Biomass Edition**) **Software**, user has to open an **Xterm** window and type (*Ubuntu OS*):

Tcl-tk packages

[user]:> sudo apt-get install libtk-img iwidgets4 bwidget

gcc/g++ packages

[user]:> sudo apt-get install gcc g++ build-essential libglew-dev

[user]:> sudo apt-get install freeglut3-dev libfreeimage-dev

Other packages

[user]:> sudo apt-get install gimp gnuplot googleearth imagemagick snap

Note: According to the operating system (OS), user has to adapt these command lines to interact with the packaging system of the corresponding Linux distribution (Debian, Fedora, OpenSuze).

INSTALLATION

To install PolSARpro v6.0.4 (Biomass Edition) Software, user has to :

1) Create a dedicated directory (for example : **polsarpro_v6.0.4**) and copy the zip file :

PolSARpro_v6.0.4_Biomass_Edition_Linux_Installer_YYYYMMDD.zip (where YYYYMMDD = date)

2) Unpack the zip file.

3) Open an **Xterm** window in the directory where **PolSARpro v6.0.4** (**Biomass Edition**) **Software** is installed and type:

[user]:> sh PolSARpro_v6.0.4_Biomass_Edition_Linux_Installation.sh

DIRECTORY STRUCTURE

Once installed, the **PolSARpro v6.0.4** (**Biomass Edition**) **Software** directory presents the following structure:

- ColorMap directory contains user defined or modified PolSARpro colour-map files
- Config directory: contains all the different software configuration files
- **GUI directory** contains all the widget window Tcl-Tk files.
- **Help directory** contains the PolSARpro Help files.
- Help-v6 directory contains new PolSARpro Help files.
- License directory contains all the PolSARpro licenses files
- Log directory will contain all the log files created for each session.
- **Soft directory** contains ready to use executable processing files and libraries.
- **TechDoc directory** contains the technical documentations relative to all the GUI Widgets and C-Routines used in PolSARpro.
- **Tmp directory** is empty after installation and is used by PolSARpro during each session.

It is strictly recommended not to change, extract, move or modify any component (tcl-tk widgets, executable processing files, colormaps, help files, PDF files...) included in the PolSARpro v6.0.4 (Biomass Edition) Software directory and / or change its structure.

RUNNING POLSARPRO V6.0.4 (BIOMASS EDITION) SOFTWARE

To run the **PolSARpro v6.0.4** (**Biomass Edition**) **Software**, start the GUI (Graphical User Interface) by double-clicking the **PolSARpro_v6.0.4_Biomass_Edition** icon located on the user desktop, or open an **Xterm** window in the directory where **PolSARpro v6.0.4** (**Biomass Edition**) **Software** is installed and type :

[user]:> wish PolSARpro_v6.0.4_Biomass_Edition.tcl