

Discover V Product documentation V Development languages V Topics V

Sign in

Windows Server

Get started Failover clustering Management Identity and access Networking Troubleshooting Related products V



chcp

chdir

chglogon

chgport

chgusr

chkdsk

chkntfs

choice cipher

cleanmgr

clip cls

cmd

cmdkey

cmstp

color comp

compact

copy

cscript

date dcdiag

dcgpofix

dcpromo

defrag

del

> dfsdiag

dfsrmig

dfsutil

diantz

dir

diskcomp

diskcopy

diskpart

> diskpart scripts and examples

diskperf

diskraid

Download PDF

Learn / Windows Server /



Article • 02/03/2023 • 10 contributors •

Applies ✓ Windows Server 2025, ✓ Windows Server 2022, ✓ Windows Server 2019, ✓ Windows Server 2016, ✓ Windows 11, ✓ Windows 10, ✓ Azure Stack HCI, versions 23H2 and 22H2

Feedback

In this article

Syntax

Examples

Related links

Changes the active console code page. If used without parameters, chcp displays the number of the active console code page.

Syntax



Parameters

Expand table

Parameter	Description
<nnn></nnn>	Specifies the code page.
/?	Displays help at the command prompt.

The following table lists each supported code page and its country/region or language:

Expand table

Code page	Country/region or language
437	United States
850	Multilingual (Latin I)
852	Slavic (Latin II)
855	Cyrillic (Russian)
857	Turkish
860	Portuguese
861	Icelandic
863	Canadian-French
865	Nordic


866	Russian
869	Modern Greek
936	Chinese

Remarks

- Only the original equipment manufacturer (OEM) code page that is installed with Windows appears correctly in a Command Prompt window that uses Raster fonts. Other code pages appear correctly in full-screen mode or in Command Prompt windows that use TrueType fonts.
- You don't need to prepare code pages (as in MS-DOS).
- Programs that you start after you assign a new code page use the new code page.
 However, programs (except Cmd.exe) that you started before assigning the new code page will continue to use the original code page.

Examples

To view the active code page setting, type:



A message similar to the following appears: Active code page: 437

To change the active code page to 850 (Multilingual), type:




If the specified code page is invalid, the following error message appears: Invalid code page

Related links

- Command-Line Syntax Key
- Code Page BitFields
- Code Page Identifiers

Feedback





Blog ☑