

Topics

• Indexing
• How to select elements

2

Indexing: referencing elements

- Extract individual entries by specifying the indices inside round brackets ().
- · Extract several entries at once by specifying
 - An array,
 - use the : operator to extract all entries along a certain dimension.

KULEUVEN 4

Comparison of the vector

• (m:n) refers to elements m through n

• ([n1, n2, ...]) specify the elements to select in a vector

• (:) refers to all elements of the vector

• (:) refers to all elements of the vector

Comparison of the vector

Vector of the vector

Comparison of the vector

Vector of the vector of the vector

Vector of the vector of the vector

**Vector of the vector of the vector

3

Subarray

- subarray: array obtained by omitting some rows and columns from a given array of X.
 The colon operator (:) can be used to select rows, columns; it can be regarded as wildcard character.
- A(:, n) selects the elements of A in column n (all rows)
- A(m, :) selects the elements of A in row m (all columns)
- A(:, n1: n2) selects all the elements of A in all rows between columns n1 and n2
- A(m1 : m2 , n1 : n2) selects all elements in rows m1 through m2 and columns n1 through n2
- A(:) returns all the elements of A, as a single column vector

```
A = [1 2 3 4; 5 6 7 8; 9 10 11 12; 13 14 15 16]
A = 4x4
1 2 3 4
5 6 7 8
9 10 11 12
13 14 15 16

n = 3
n = 3
A.col.n = A(r,n)
A.col.n = 4x1
3
7
111
15

m = 2
m = 2
M.row m = A(m,r)
A.row m = 1x4
5 6 7 8
```

KU LEUVEN

5

Deletion

- Assigning [] deletes the corresponding entries from the matrix.
- · Only deletions that result in a rectangular matrix are allowed.

KU LEUVEN

9

Assignment of elements

- Assignment operations follows the same rules as referencing and then specify the new values on the right hand side.
- The right must be either a scalar value, or a matrix with the same dimensions as the resulting indexed matrix on the left.
- MATLAB automatically expands scalar values on the right to the correct size

>>	A = 0	nes(3,	5)			
Α -						
	1	1	1	1	1	
	1	1	1	1	1	
	1	1	1	1	1	
>> A(3,2) = 5						
Α :						
	1	1	1	1	1	
	1	1	1	1	1	
	1	5	1	1	1	
>>	>> A(:,1:3:end) = 8					
Α :						
	8	1	1	8	1	
	8	1	1	8	1	
	8	5	1	8	1	

KU LEUVEN

•

Expansion

- Add one or more elements to a matrix by placing them outside of the existing row and column index boundaries. MATLAB automatically pads the matrix with zeros to keep it rectangular.
- · No error message!

>> A = magic(3)

KU LEUVEN

8



