FUN FILTER PACK

User Manual

Three simple filters. Just the controls you need.






01 HIGH PASS

02 LOW PASS

03 BAND PASS

English



Version 1.1.0 / 2026.11.02

01

Three filters. A focused workflow.

HIGH PASS / LOW PASS / BAND PASS

FUN Filter Pack contains three purpose-built effects: High Pass, Low Pass, and Band Pass. Each keeps the interface focused on cutoff adjustment. Read the on-screen values, then use your ears to decide what works for the source.

01

HIGH PASS

Attenuates low frequencies to clean up unwanted bottom end.

02

LOW PASS

Attenuates high frequencies to shape brightness and bandwidth.

03

BAND PASS

Uses two cutoff points to define the frequency region that passes.

Quick start

1. Insert the desired filter on an audio track in your DAW.
2. Drag the cutoff knob vertically to set the frequency.
3. Hold Shift while dragging for finer adjustments.
4. Listen during playback, and automate the cutoff in the DAW if needed.

Interface and readouts

The default editor scale is 60%. High Pass and Low Pass open as squares (266 × 266 px); Band Pass opens at 2:1 (532 × 266 px). The interface can be resized to approximately 50–200%. Readouts switch between Hz and kHz.

High Pass

HIGH PASS

Attenuates content below the selected cutoff frequency. Use it when unwanted low-frequency energy is distracting from the part you want to keep.



Range	Default
20 Hz - 3 kHz	200 Hz

Nominal slope	Change transition
24 dB/oct	~5 ms

CUTOFF FREQUENCY

Ways to use it

- Reduce low rumble on vocals or effects
- Control unnecessary sub-bass energy
- Make room for the low end of another layer

Good to know

The adjustable range is 20–3,000 Hz. The 200 Hz default is a starting state, not a recommended setting for every source.

Low Pass

LOW PASS

Attenuates content above the selected cutoff frequency. Use it to reduce brightness, narrow the bandwidth, or push a layer further into the background.



Range	Default
20 Hz - 20 kHz	20 kHz

Nominal slope	Change transition
24 dB/oct	~5 ms

CUTOFF FREQUENCY

Ways to use it

- Tame overly bright material
- Soften a background texture
- Automate cutoff for evolving timbre


Good to know

The default is 20 kHz. The upper-frequency behavior reflects the implemented matched/decramped low-pass design.

Band Pass

BAND PASS

HIGH PASS CUTOFF on the left removes the low end; LOW PASS CUTOFF on the right removes the high end. Together they define the passing region.



Parameter specifications

Parameter	Range	Default
High Pass Cutoff	20 Hz - 20 kHz	200 Hz
Low Pass Cutoff	20 Hz - 20 kHz	2.5 kHz

Ways to use it

- Create a narrow, telephone-like effect
- Highlight the midrange of a sound
- Move both cutoffs to animate the passband

Good to know

Normally set HP below LP. If the controls cross, the DSP limits effective cutoffs to a safe ordering.

Controls, specifications, troubleshooting

WORKFLOW / TECHNICAL REFERENCE

A compact reference for the shared controls and practical host behavior of all three filters.

Drag	Move a knob vertically to change its cutoff.
Shift + drag	Make finer cutoff changes.
DAW automation	Cutoff is exposed as a host parameter.

State, audio, and host

- Parameter values are stored and restored with the DAW's plug-in state.
- Use the effects on mono or stereo audio buses.
- Cutoff changes use an approximately 5 ms crossfade between old and new filter banks. This reduces abrupt changes but cannot guarantee a click-free result.

If something goes wrong

The plug-in does not appear in my DAW

Check that the complete built VST3 bundle is in a location scanned by your host. On Windows, the actual binary inside Contents/x86_64-win is required. Rescan plug-ins if needed.

The size or parameter value looks different

The initial GUI is 60%, but a host may restore the previous editor size. Check saved plug-in state and automation if cutoff values differ.

This manual is based on the FUN Filter Pack 1.1.0 GUI and the provided source specifications. Screenshots show the 60% interface.