Repair journey at a glance

CUSTOMER-TO-DELIVERY WORKFLOW

One repair request moves through five accountable roles. Customers stay in control of approval, while each handoff is recorded in the booking timeline.

01 **BOOK**
Customer verifies email, selects device and repair, then submits pickup details.

02 **ASSIGN**
Admin or regional operations assigns a verified centre and an active technician.

03 **COLLECT**
Technician schedules the visit, verifies custody and records transit.

04 **DIAGNOSE & QUOTE**
Service centre receives the device, diagnoses it and sends the quotation.

05 **APPROVE & REPAIR**
Customer accepts or rejects the quote; repair starts only after approval.

06 **QUALITY & RETURN**
Service centre passes quality checks; technician returns the device; customer closes the order.

Status path

BOOKED -> ASSIGNED -> VISIT_SCHEDULED -> PICKUP_VERIFIED -> IN_TRANSIT -> RECEIVED_AT_CENTRE -> DIAGNOSIS -> QUOTE_SENT -> CUSTOMER_APPROVED -> REPAIRING -> QUALITY_CHECK -> READY_FOR_DELIVERY -> OUT_FOR_DELIVERY -> DELIVERED -> CLOSED

Branches: a rejected quote returns the device without repair; a parts delay can pause repair before work resumes.

Role responsibilities

ACCESS AND OPERATIONAL OWNERSHIP

Customer

- Verifies email with a one-time code before the account is created.
- Creates repair requests, tracks every milestone, and approves or rejects the quote.
- Receives booking and progress messages at the account email.

Field technician

- Works only on jobs assigned to their profile.
- Schedules pickup, records custody verification and transit, then handles the return delivery.

Service partner

- Receives devices at the linked verified service centre.
- Records diagnosis and sends the quote. Repairs start only after approval; service centre then completes quality control.
- May assign technicians linked to its centre.

Regional and admin control

ASSIGNMENTS AND ESCALATION

Regional operations

- Monitors work in the assigned region and coordinates local partner and technician assignments.
- Cannot assign users outside the region or change national administrator roles.

Super administrator

- Invites and manages all user roles, including customers; links operations users to valid regions or verified centres.
- Assigns work, manages workflow, business enquiries, catalogue/pricing and email settings.

Assignment safeguards

- Technicians and service partners must be active and linked to a verified service centre.
- Repair starts only after customer approval. Status changes cannot silently overwrite concurrent updates.

Email and security

ADMINISTRATOR SETUP CHECKLIST

Configure delivery

- In Admin -> SMTP settings, choose Gmail, Zoho Mail or Other / Custom. Enter the provider host, port, TLS option, username, app password, sender address and reply-to.
- Save the settings, then send a test email before enabling registrations. SMTP credentials are encrypted on the server and never returned to the browser.

Set notification recipients

- Add operations addresses as comma-separated internal recipients. New accounts, bookings, business enquiries and booking progress messages include these recipients.
- Add optional comma-separated CC addresses to copy routine service emails. OTP codes, invitation links and password-reset links are intentionally never copied.

Protect account access

- The six-digit email code expires after 10 minutes, allows up to five guesses, and can only be resent after the cooldown.
- Admin invitations and password resets use one-time links; the recipient chooses their own password.
- Only active administrators may change roles. The final active admin cannot disable or demote itself or another final administrator.

Operational handoffs

- The technician records pickup and delivery verification references in the order timeline.
- The customer receives each booking milestone at their registered email.