Test scenario	Test case	Test case description	Test data	Steps Expected result
Scenario: User attempts to login via email	1	User attempts to login with valid email address linked to an existing voxy account	a valid email address linked to a voxy account	 Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Email" option (should be checked by default) Input a valid email address linked to a voxy account Click on "continue"
	2	User attempts to login with properly formatted email address NOT linked to an existing voxy account, but the internet connection is lost	email address: test@tesmail.c om	' ` the unauthorized
	3	User attempts to login while leaving the email field empty		 Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Email" option (should be checked by default) Try to click on "continue"
	4	User attempts to login with an invalid email address	email address: abc	 Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Email" option (should be checked by default) Input an valid email address Try to click on "continue"

	5	User attempts to login with a valid email address, but not linked to any valid voxy accounts	email address: test@tesmail.c om	2.	Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Email" option (should be checked by default) Input a valid email address NOT linked to a voxy account Click on "continue"	A message regarding the unauthorized login attempt will be shown as a pop-up
	6	User attempts to input data on the "email" field while having the "mobile number" option selected		2.	Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Attempt to input data on the "email" field	The user will be unable to input data
	7	User attempts to login filling the "mobile number" field with an email address		2.	Access voxy's login page: https://web-stage.voxy. com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Input a valid email address on the "Mobile Number" field Try to click on "continue"	User will be unable to click the "continue" option
Scenario: User attempts to login via mobile number	1	User attempts to login with a valid US mobile number linked to a voxy account	a valid US mobile number linked to a voxy account	2.	Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Input a valid mobile number linked to a voxy account Click on "continue"	User should be successfully taken to the next step

2	User attempts to login with a valid non US mobile number linked to a voxy account	a valid non US mobile number linked to a voxy account	 Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Click on the flag icon and chose the country of the mobile number to be input Input a valid mobile number linked to a voxy account from the previously selected country Click on "continue"
3	User attempts to login with a valid mobile number NOT linked to a voxy account	mobile number (US): (541) 754-3010	 Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Input a valid mobile number NOT linked to a voxy account Click on "continue"
4	User attempts to login while leaving the mobile number field empty		 Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Try to click on "continue"
5	User attempts to login with an invalid mobile number	mobile number: 123	 Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Input an valid mobile number

			4.	Try to click on "continue"	
6	User attempts to input data on the "mobile number" field while having the "email" option selected		2.	Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Email" option (should be checked by default) Attempt to input data on the "mobile number" field	The user will be unable to input data
7	User attempts to login filling the "email" field with a mobile number	mobile number (US): (541) 754-3010	2.	Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Email" option (should be checked by default) Input a valid mobile number on the "Email" field Try to click on "continue"	User will be unable to click the "continue" option
8	User attempts to login with a valid mobile number NOT linked to a voxy account, but the connection is lost	mobile number (US): (541) 754-3010	6.7.8.	Access voxy's login page: https://web-stage.voxy.com/v2/#/login/ Click on the "Mobile Number" option (should NOT be checked by default) Input a valid mobile number NOT linked to a voxy account Turn off the internet connection Click on "continue"	A message regarding the unauthorized login attempt will be shown as a pop-up