

Account and Authentication

FlowStack Knowledge Base | Tenant: b2b-saas-demo

Document metadata

Title: Account and Authentication

Category: account / security

Tenant: b2b-saas-demo

Version: 2.0

Last updated: 2026-09-10

How do I sign in to FlowStack?

Go to flowstack.com/signin and enter the email associated with your account. If your workspace uses password authentication, enter your password. If your workspace uses SSO, you'll be redirected to your identity provider. Magic link sign-in is also available: enter your email and click the sign-in link sent to your inbox.

What sign-in methods are supported?

FlowStack supports password sign-in, magic link sign-in, Google SSO, Microsoft SSO, and SAML-based SSO (Enterprise plans). The available methods depend on your workspace configuration. Workspace owners can enable or disable methods under Settings → Authentication.

I forgot my password. How do I reset it?

Go to the sign-in page and click "Forgot password". Enter your email and check your inbox for a reset link. The link expires after 60 minutes. If you don't see the email within 5 minutes, check your spam folder. If you still don't receive it, your workspace may require SSO or magic link sign-in instead.

How do I change my password?

Sign in, then go to Settings → Profile → Security → Change Password. Enter your current password and the new one. Passwords must be at least 12 characters and include at least one uppercase letter, one lowercase letter, and one number. Passwords cannot reuse any of the last 5 passwords.

Does FlowStack support multi-factor authentication?

Yes. FlowStack supports TOTP-based MFA (Google Authenticator, Authy, 1Password, etc.) and hardware security keys (WebAuthn/FIDO2). Enable MFA under Settings → Profile → Security → Two-Factor Authentication. Workspace owners can require MFA for all members under Settings → Authentication.

How do I set up MFA?

Go to Settings → Profile → Security → Two-Factor Authentication → Enable. Scan the QR code with your authenticator app, enter the 6-digit code to confirm, and save your recovery codes in a safe place. Recovery codes are shown once and can be regenerated at any time.

What if I lose my MFA device?

Use one of your saved recovery codes to sign in. If you've lost both your device and your recovery codes, an account owner or admin in your workspace can reset MFA for you from Settings → Members. If you're the sole owner, contact support to begin identity verification.

My account is locked. What do I do?

Accounts are locked after 10 consecutive failed sign-in attempts within 15 minutes. The lock lifts automatically after 30 minutes. If you need immediate access, use the password reset flow. Workspace owners can unlock a member's account from Settings → Members → Unlock.

What does "suspicious sign-in activity" mean?

FlowStack flags a sign-in as suspicious when it comes from an unusual location, device, or IP address. You'll receive a notification email with details and can mark the sign-in as trusted or revoke it from Settings → Profile → Security → Active Sessions. If you don't recognize the activity, change your password immediately and enable MFA.

How do I see active sessions?

Go to Settings → Profile → Security → Active Sessions. This page lists every device currently signed in, with location, browser, and last activity timestamp. You can revoke any session individually or click "Sign out everywhere" to end all sessions.

How do I update my profile information?

Go to Settings → Profile. You can change your display name, email, timezone, language, and profile photo. Changing your email requires confirmation from the new address before it takes effect. Changing the email does not affect your sign-in method if you use SSO.

How do I change the email on my account?

Go to Settings → Profile → Email → Change Email. Enter the new address. FlowStack sends a confirmation link to the new address. Click the link to complete the change. Your old email can still be used for 24 hours to sign in during the transition.

How do I delete my account?

Account deletion is a workspace-owner action. Go to Settings → Workspace → General → Delete Workspace. You'll be asked to type the workspace name to confirm. Deletion removes all workflows, execution history, integrations, and member access. The action is irreversible after a 7-day grace period. Individual users who are not workspace owners can leave a workspace from Settings →

Profile → Leave Workspace.

What is workspace ownership?

Each workspace has exactly one owner. The owner controls billing, workspace deletion, SSO configuration, and role assignments. Ownership can be transferred to another admin from Settings → Members → Transfer Ownership.

Someone accessed my account without permission. What should I do?

Change your password immediately and enable MFA. Then go to Settings → Profile → Security → Active Sessions and revoke any unfamiliar sessions. Review audit logs under Settings → Workspace → Audit Log for unauthorized actions. Contact support@flowstack.com with the approximate time and any unusual activity you noticed. Treat this as security-sensitive.