Task 3: Bug Identification and Reporting

1. **Bug Id:** Bug_001

2. **Description:** While testing the product listing page with the user account `problem_user`, I noticed that none of the products display their actual pictures. Instead, the exact same picture of a dog is showing up on every item card, which makes it impossible for a shopper to see what they are buying

3. **Steps to Reproduce:** Go to https://www.saucedemo.com/.

   1. Enter username `problem_user` and password `secret_sauce`.
   2. Click the **Login** button.
   3. Look at the product images on the inventory page.

4. **Expected Result:** Each product should display its own correct photo (like the backpack photo for the backpack, bike light photo for the bike light, etc.).

5. **Actual Result:** All products show the same dog picture (`sloth-400x300.jpg`).

1. **Bug Id:** Bug_002

2. **Description:** On the inventory catalog page, when logged in with `problem_user`, selecting any sorting option from the product filter dropdown (e.g., Price: low to high, Name: Z to A) does not reorder the items. The products remain frozen in their default order.

3. **Steps to Reproduce:**

   1. Go to https://www.saucedemo.com/ and log in using username problem_user.
   2. On the inventory page, click on the top-right sorting dropdown.
   3. Select the option Price (low to high).
   4. Observe the product cards and prices on the screen.

4. **Expected Result:** the inventory catalog should be reordered immediately so that products are arranged from lowest price ($7.99) to highest price ($49.99).

5. **Actual Result :** The products do not sort; they stay in the exact same default order, and sorting fails completely.

1. **Bug Id:** Bug_003

2. **Description:** On the checkout information page, the Zip/Postal Code field does not check if the user entered valid numbers or letters. When I typed random symbols like!@#$%^&*, the site accepted it without any warning and took me straight to the next overview step.

3. **Steps to Reproduce:**

1. Log in with `standard_user`, add any item to the cart, and click **Checkout**.
2. Type valid names in First Name and Last Name.
3. In the **Zip/Postal Code** box, type symbols!@#$%^&*.
4. Click the **Continue** button

4. **Expected Result:** The system should stop the user and show an error message saying that the postal code format is invalid.

5. **Actual Result:** The form accepts the symbols and opens the payment overview page without any check.