Instructions OPENVPN for Windows – RH BOX

Install/configure OpenVPN

1. Download OpenVPN
   https://swupdate.openvpn.org/community/releases/openvpn-install-2.4.3-I601.exe (or newer version)

2. How to install OpenVPN
   https://openvpn.net/index.php/access-server/docs/admin-guides-sp-859543150/howto-connect-client-configuration/395-how-to-install-the-openvpn-client-on-windows.html

3. After the installation, you should navigate to:
   C:\Program Files\OpenVPN\config

4. After receiving the OpenVPN user/vessel credentials, extract the two zip files. Inside the config folder, you should paste the folder containing your personal credentials.


Now your setup is ready!

Connect with OpenVPN

1. If you start OpenVPN, you will find In the right lower corner the OpenVPN icon as shown below:

2. Right click on it. When you perform a "right" click on the icon, you will see a list with all available credentials in your config file.

3. Select the correct VPN-connection (name can be different) and click on connect. If the connection is successful, you should see the icon lit up in green.


4. You can use two VPN connections simultaneously, navigate to: C:\Program Files\TAP-Windows\bin and click addtap.bat file.

Instructions OPENVPN for Macintosh – RH BOX

Install/configure OpenVPN
1. Download and install the tunnelblick application.
   https://tunnelblick.net/release/Tunnelblick_3.7.9_build_5320.dmg

After installation, you will find in the upper right corner the Tunneblick icon as shown below:

Now your setup is ready!

Connect with Tunnelblick
1. After receiving the OpenVPN user/vessel credentials, navigate to your OpenVPN folder.


2. To install a configuration file, drag and drop it on the Tunnelblick icon in the menu bar or on the list of configurations in the 'Configurations' tab of the 'VPN Details' window.

   To install multiple configuration files at one time, select all the files and then drag and drop all of them.

3. Click on the icon, you will see a list with all available credentials that are imported.

4. Select the correct VPN-connection (name can be different) and click on connect.
   If the connection is successful, you should see the "check icon" at the left side of the VPN credential. You can use two VPN connections simultaneously.