CS 218 – Assignment #5

Purpose: Learn to use arithmetic instructions, control instructions, compare instructions, and


conditional jump instructions.

Due: Tuesday (6/18)

Points: 50

Assignment:

Write a simple assembly language program to calculate the some geometric information for a series of cubes; areas and volumes. The information for the cubes are stored in an array. Once the areas and volumes are computed, the program should find the minimum, maximum, middle value, sum, and average for the areas and volumes.



The formulas for cube area and volume are as follows:

$$cubeAreas[i] = 6 * sides[i]^{2}$$

 $cubeVolumes[i] = sides[i]^{3}$

Where i represents the specific cube information in the array (i.e., the index).

The side lengths are stored in a word-sized array named *sides*. The cube areas must be calculated and stored into the word-sized array named *cubeAreas*. The areas sum, *caSum*, must be calculated and stored as a double-word. The cube volumes must calculated and stored into the double-word sized array named *cubeVolumes*.

All data must be treated as unsigned values (i.e., must use of MUL and DIV, not IMUL or IDIV).

Note, for an odd number of items, the middle value is defined as the middle value. For an even number of values, it is the integer average of the two middle values. The middle value is just the middle value of the array and as such is not statistically meaningful.

Do *not* change the sizes/types of the provided data sets. You may declare additional variables as needed.

Submission:

When complete, submit:

• A copy of the source file via the class web page.
Assignments received after the start time of class will not be accepted.

Assignment #5 Provided Data Sets:

Use the following are the provided data declarations for assignment #5.

Note 1, a copy of the data set is provided on the class web site.

Note 2, the assembler **is** case sensitive.

```
______
  Provided Data Set
sides
                10,
                    14,
                         13,
                              37,
                                  54
          dw
          dw
                14,
                    29,
                         64,
                              67,
                                  34
          dw
                31,
                    13,
                         20,
                              61,
                                  36
                14,
                    53,
                         44,
                              19,
          dw
                                  42
                    52,
                         31,
                                  56
                44,
                              42,
          dw
          dw
                15,
                    24,
                         36,
                              75,
                                  46
          dw
                27,
                    41,
                         53,
                              62,
                                  10
                                  15
                     4,
                         73,
                              31,
          dw
                33,
          dw
                5,
                    11,
                         22,
                              33,
                                  70
                15,
                    23,
                         15,
                              63,
                                  26
          dw
                16,
                    13,
                         64,
                              53,
                                  65
          dw
                         57,
                                  34
          dw
                26,
                    12,
                              67,
                                  15
          dw
                24,
                    33,
                         10,
                              61,
          dw
                38,
                    73,
                         29,
                              17,
                                  93
                    73,
          dw
                64,
                         74,
                              23,
                                  56
                9,
                     8,
                         4,
                              10,
                                  15
          dw
                    23,
                13,
                         53,
                              67,
                                  35
          dw
          dw
                14,
                    34,
                         13,
                              71,
                                  81
          dw
                17,
                    14,
                         17,
                              25,
                                  53
                    73,
                                  13
          dw
                23,
                         15,
                               6,
length
          dd
               100
               0
caMin
          dw
               0
caMid
          dw
caMax
          dw
               0
caSum
          dd
               0
caAve
          dw
               0
cvMin
          dd
               0
cvMid
          dd
               0
          dd
               0
cvMax
               0
cvSum
          dd
cvAve
          dd
  _____
  Uninitialized data
section
          .bss
cubeAreas
               resw 100
cubevolumes
               resd 100
```

Note, the ".bss" section is for uninitialized data. The "resd" is used to reserve double-words and the "resw" is used to reserve words.