Inserting an Image in a Document

LibreOffice Writer allows to work on images, shapes, charts and diagrams by providing various tools. The image file can be inserted into a document using different ways.

Using Insert Image Option

Step 1 Open the document to insert an image in LibreOffice Writer.

Step 2 Place the cursor where you want to insert an image.

Step 3 Select and click on Insert > Image from menu bar.

Step 4 An Insert Image dialog box will open which will allow to choose the picture file to be inserted.

Step 5 Select the file and click on Open button to insert an image in document.

Using Drag and Drop option

Step 1 Open the document to insert an image in LibreOffice Writer.

Step 2 Open a file browser window (Win+E) and select the image file to be inserted.

Step 3 Drag the image into the document.


Step 4 Drop it, where you want it to appear in the document.

READERS VENUE


Copy and Paste method

Step 1 Open the document to insert an image in LibreOffice Writer.

Step 2 Copy the image file stored in computer.



Step 3 Paste the image file in the document.



Inserting an image using any of the above described method saves a copy of image file in the document wherever image is inserted, that means, the image gets embedded in the document.

If multiple copies of the same image are required to be inserted in the document, it is beneficial to save the link of image instead of inserting the image.








Inserting a link, stores its reference instead of the image itself, thereby reduces the size of the document, because actual image is saved only once as a separate file along with the document.

Linking an Image in a Document

In Insert Image dialog box, check the Link option .

Keyboard shortcut to link an image – drag and drop the image while holding the Ctrl+Shift keys.



Modifying an Image

The image toolbar automatically appears when an image is inserted or selected in the document.

If you want to keep it always on screen, click on **View > Toolbars > Image** from the menu bar.



Image Toolbar





Image Filter

There are 11 types of filters available for improving an image.

READERS VENUE



Image Mode

Image can be changed to black and white, gray-scale or a watermark.



Crop

Cuts off non-desirable part of the image.

READERS VENUE



Flip Horizontally

Flips the image Horizontally by 180 degree.

Flip Vertically

Flips the image Vertically by 180 degree.



Rotate 90 degree left.

Rotate 90 degree right.

Rotate. (At your desired angle)

READERS VENUE



Transparency Makes an image transparent by using the value provided in percentage .



Colour

Using Drop Down list Red, Blue or Green colour can be modified or adjustment for brightness, contrast and gamma can be made.

READERS VENUE

Image Filters

Invert Inverts the colour values of coloured image.

Smooth Softens the contrast of image.


Sharpen Increases the contrast of image.

Remove Noise Removes single pixels from the image.

Solarisation Reverses the tone. Dark appears light and light appears dark.

Aging Simulates the effect of time on picture.

Posterise Makes a picture appear like painting by reducing colours in the image.




READERS VENUE

Image Filters

Charcoal Sketch	Changes image as charcoal sketch.
Relief	Adjusts light source to create shadow.
Mosaic	Joins group of pixels into a single area of one colour.

READERS VENUE



Resizing an Image

Resizing is the process of reducing or enlarging the size of the image.

Step 1 **Click on the image, eight sizing handles surrounding the image will appear on the screen.**

Step 2 **Position the pointer over one of the sizing handles. The pointer changes shape indicating the direction of resizing.**

Step 3 **Click and drag to resize the image.**

Step 4 **Release the mouse button when satisfied with the new size and observe the size of the image is reduced.**

By dragging the corner handles, one can resize both the width and the height of the image simultaneously, while the other four handles only resize one dimension at a time.

Deleting an Image

To delete the image, just select the image by clicking on the image and press the Delete key.

READERS VENUE

Drawing Objects



To display Drawing Toolbar in the Writer window, click on View > Toolbars > Drawing.

There are many default drawing objects used to create designs in document. To use them –

Step 1 Place the cursor in the document where you want the drawing to be placed (anchored).

Step 2 Select the tool from the Drawing toolbar.

Step 3 Place the pointer on document where you want the image to appear then click-and-drag to create the drawing object.

Step 4 Release the mouse button to finish drawing.

Step 5 To cancel the selected drawing function, press the Esc key or click the Select icon (the arrow) on the Drawing toolbar.

Setting or Changing Properties of Drawing Object

To set the properties before drawing the object:

Step 1 From the Drawing Toolbar, select the object you want to draw.

Step 2 From Drawing Object Properties Toolbar, click on the icon of property to be modified.

Step 3 Change the value of parameter.

Step 4 Repeat steps 2 and 3 to change all desired properties.

Step 5 Draw the desired figure.

When properties are modified before creation, it is known as setting default value(s).

Changes done in properties of an object, before creating it, are available only for current session.

READERS VENUE

Steps for changing properties of the object after drawing it:

Step 1 Select the object whose properties are to be modified.

Step 2 Follow steps 2 to 5 of the previous process of setting Properties before drawing an object.

READERS VENUE

Resizing and Grouping objects

Follow the given steps to resize a drawing:

Step 1 Select the object to be resized. All eight handles on the corners and edges will be visible.

Step 2 Click on any of the handles and drag it to its new place. The object will be scaled up or down, depending on your action.

Step 3 For resizing and maintaining original shape of drawing, use corner handles.

READERS

Grouping drawing objects

LibreOffice Writer allows grouping different shapes, to behave as a single entity without affecting their size and position.

Once grouped, all shapes belonging to that group become its member and a change applied on one member works on all.

Step 1 Select the object by clicking over it.

Step 2 Hold the Shift key and keep on selecting all other objects by clicking on it to be included in the group.

Step 3 Select a group tool from Drawing Object Properties Toolbar. Alternatively, selecting from main menu **Format › Group › Group** will also do same work.

Step 4 This process will group the selected drawing objects.

Positioning Image in the Text

Once the task of creating, formatting, resizing and grouping the drawing object is complete, it has to be positioned in the document with text and other image or drawings.

Positioning of an image is controlled by four settings.

(i) Arrangement
(ii) Anchoring
(iii) Alignment
(iv) Text Wrapping

READERS VENUE

These settings can be accessed using three ways – by using Format menu, by using context menu after right clicking on the object, by using Drawing Object Properties Toolbar for changing the properties of the drawings.

Positioning Image in the Text

Arrangement

In Overlapping objects arrangement determines the position of the current drawing with respect to other drawings or text.

Table 2.3: Description of Image arrangement tools

Tool	Effect
Bring to Front	Place image on top of all objects / images
Forward One	Bring image one level up, when there are overlapping images
Back One	Sends image one level down in overlapping images
Send to Back	Place image at the bottom of all objects/ images
To Foreground	Moves the drawing object in front of the text
To Background	Moves the drawing object behind the text

Image/ Drawing Objects

Drawing Objects

Positioning Image in the Text

Anchoring

It acts as a reference point for image or drawing. Anchoring allows an image to retain its position to a page, paragraph, character or frame.

Image can be anchored to Page, Paragraph, Character or Frame. So whenever a page, paragraph, character or frame is aligned, the anchored image moves along with it.

READERS VENUE




Fig. 2.32: Anchored tool with its options

Positioning Image in the Text

Alignment

It allows the vertical or horizontal placement of the image with respect to its anchor. Alignment tools are located under Drawing Properties Toolbar.

Text Wrapping

It allows the placement of image in relation to text. Text Wrapping tools are available under Drawing Object Properties Toolbar.

Tool	Wrapping Effect
Wrap off	Text is placed above and below the image
Page Wrap	Text flows around the image. Moving an image will rearrange the text on the page
Optimal Page wrap	In Page Wrap, if the space between image and margin is less than 2 cm then text will not be placed on that side
Wrap left	Text is placed on left side of the image
Wrap right	Text is placed on the right side of the image
Wrap through	Superimposes the image on the text