Lab 10: Build DynamoDB table with auto scaling

In this lab, we will create an Amazon DynamoDB table and configure auto scaling for read and write capacity to handle variable workloads efficiently.

STEPS

Step 1: Create DynamoDB Table

1. Go to AWS Console -> DynamoDB Tables -> Create Table.
2. Configure:
   - Table Name: Orders-Table.
   - Partition Key: OrderID (String).
   - Sort Key- Optional: (e.g., CustomerID).

3.In Table settings, select Customize settings and configure the Capacity Mode as Provisioned.


4.Configure Read Capacity Auto Scaling:

- Minimum: 5.
- Maximum: 50.
- Target Utilization: 70%.


5.Configure Write Capacity Auto Scaling.


- Minimum: 5.
- Maximum: 50.
- Target Utilization: 70%.

6. Click Create Table and your Dynamo DB table with auto scaling will be ready.




Create table | Amazon DynamoDB
Ask Gemini
ap-south-1.console.aws.amazon.com/dynamodbv2/home?region=ap-south-1#create-table
Search
[Alt+S]
Asia Pacific (Mumbai)
Gitesh Patil (290849813857)
Gitesh Patil
DynamoDB > Tables > Create table
Create table
Table details Info
DynamoDB is a schemaless database that requires only a table name and a primary key when you create the table.
Table name
This will be used to identify your table.
Orders-Table
Between 3 and 255 characters, containing only letters, numbers, underscores (_), hyphens (-), and periods (.).
Partition key
The partition key is part of the table's primary key. It is a hash value that is used to retrieve items from your table and allocate data across hosts for scalability and availability.
OrderID
String
1 to 255 characters and case sensitive.
Sort key - optional
You can use a sort key as the second part of a table's primary key. The sort key allows you to sort or search among all items sharing the same partition key.
CustomerID
String
1 to 255 characters and case sensitive.
Table settings
Default settings
The fastest way to create your table. You can modify most of these settings after your table has been created. To modify these settings now, choose 'Customize settings'.
Customize settings
Use these advanced features to make DynamoDB work better for your needs.
Table class Info
Select table class to optimize your table's cost based on your workload requirements and data access patterns.
Choose table class
DynamoDB Standard
The default general-purpose table class. Recommended for the vast majority of tables that store frequently accessed data, with throughput (reads and writes) as the dominant table cost.
DynamoDB Standard-IA
Recommended for tables that store data that is infrequently accessed, with storage as the dominant table cost.
Capacity calculator Info
Read/write capacity settings Info
Capacity mode
On-demand
Simplify billing by paying for the actual reads and writes your application performs.
Provisioned
Manage and optimize your costs by allocating read/write capacity in advance.
Read capacity
Auto scaling Info
Dynamically adjusts provisioned throughput capacity on your behalf in response to actual traffic patterns.
On
Off
Minimum capacity units
1
Maximum capacity units
10
Target utilization (%)
70
Write capacity
Auto scaling Info
Dynamically adjusts provisioned throughput capacity on your behalf in response to actual traffic patterns.
On
Off
Minimum capacity units
5
Maximum capacity units
10
Target utilization (%)
70
Warm throughput Info
Increasing the warm throughput value pre-warms your table to handle planned peak events without throttling or scaling delays. By default, warm throughput values are visible for all tables and global secondary indexes. These values automatically adjust as you increase your provisioned throughput or on-demand consumption without extra charges, but if you choose to change them manually, additional charges apply. Learn more about Amazon DynamoDB pricing
Read units per second
Keep default values
Increase warm throughput
Read units per second
1
Write operations per second
Keep default values
Increase warm throughput
Write units per second
5
Secondary indexes Info
Delete
Create global index
Create local index
Name
Type
Partition key
Sort key
Projected attributes
Warm throughput
No indexes
Use secondary indexes to perform queries on attributes that are not part of your table's primary key.
Create vector index
Estimated read/write capacity cost
Here is the estimated total cost of provisioned read and write capacity for your table and indexes, based on your current settings. To learn more, see Amazon DynamoDB pricing for provisioned capacity.
Total read capacity units
5
Total write capacity units
5
Region
ap-south-1
Estimated cost
$3.31 / month
Encryption at rest Info
All user data stored in Amazon DynamoDB is fully encrypted at rest. By default, Amazon DynamoDB manages the encryption key, and you are not charged any fee for using it.
Encryption key management
AWS owned key Learn more
The key is owned and managed by DynamoDB. You are not charged additional fees for using this key.
AWS managed key Learn more
The key is stored in your account and managed by AWS Key Management Service (KMS). AWS KMS charges apply.
Customer managed key Learn more
The key is stored in your account and managed by you. AWS KMS charges apply.
Deletion protection Info
Deletion protection is turned off by default. Deletion protection protects the table from being deleted unintentionally. You can turn on deletion protection now, and you can also turn it on after the table has been created.
Add new statement
Turn on deletion protection
CloudShell
Agent Toolkit for AWS
Feedback
Console Mobile App
© 2026, Amazon Web Services, Inc. or its affiliates.
Privacy
Terms
Cookie preferences


Search
[Alt+S]
Asia Pacific (Mumbai)
Gitesh Patil (290849813857)
Gitesh Patil
DynamoDB > Tables > Create table
Add new statement
JSON Ln 1, Col 0
Security: 0
Errors: 0
Warnings: 0
Suggestions: 0
Preview external access
Tags Info
Tags are pairs of keys and optional values, that you can assign to AWS resources. You can use tags to control access to your resources or track your AWS spending.
No tags are associated with the resource.
Add new tag
You can add 50 more tags.
Cancel
Create table


Search
[Alt+S]
Asia Pacific (Mumbai)
Gitesh Patil (290849813857)
Gitesh Patil
DynamoDB > Tables
DynamoDB
Dashboard
Tables
Explore items
PartiQL editor
Backups
Exports to S3
Imports from S3
Integrations
Reserved capacity
Settings
Tables (1) Info
Last updated
September 11, 2026, 12:05 (UTC+5:30)
Actions
Delete
Create table
Find tables
Filter by tag
Any tag key
Filter by tag value
Any tag value
1
Name
Status
Partition key
Sort key
Indexes
Replication Regions
Deletion protection
Favorite
Read capacity mode
Orders-Table
Active
OrderID (S)
CustomerID (S)
0
0
Off
Provisioned (1)