Philippine Christian University
Sampaloc I, Dasmariñas, Cavite
https://dasma.pcu.edu.ph

Configuring SSH Remote Access on Ubuntu Server

Objective

Set up an Ubuntu Server with SSH (Secure Shell) remote access and connect to it from a host desktop machine using Bridged Network mode.

Operating System Installation

Install Ubuntu Server

1. Start the VM and boot from the Ubuntu Server ISO
2. Follow the installation wizard:
    - Profile setup: Create a user account (e.g., server / server123)
    - Install OpenSSH server: **Check this option** (Important!)
    - Selected software: **None** (Standard Ubuntu Server)
3. Wait for installation to complete and reboot

Network Configuration

Configure Network Mode

For VirtualBox:

1. Power off the VM (if running)
2. Go to **Settings** → **Network**
3. **Adapter 1**: Enable Network Adapter
4. **Attached to**: Select **Bridged Adapter**
5. **Name**: Select your host's physical network adapter (Wi-Fi/Ethernet)
6. Click **OK**

For VMware:

1. Power off the VM
2. Go to **VM Settings** → **Network Adapter**

3. Select **Bridged** mode

4. Click **OK**

Install/Verify SSH Server


Server: Install SSH on the server (if not already installed):

- sudo systemctl status ssh – for checking the SSH status.
- sudo apt update – updating the your server.
- sudo apt install openssh-server -y –installing the SHH.
- sudo systemctl enable ssh – enabling the SSH to your unit. (SERVER/DESKTOP)
- sudo systemctlstartssh – starting the SHH to your unit. (SERVER/DESKTOP)

Bridged makes the server behave like a separate PC in your LAN.

1. Find the Server's IP


Inside the VM, run:



From the desktop, connect to the server: ssh username@192.168.1.120

2. Connect from Desktop


From your host desktop:




Submission Requirements

1. **Screenshots (labeled clearly):**
   - VM network settings showing Bridged Adapter
   - Server IP address (output of ip a or hostname -I)
   - SSH service status (sudo systemctl status ssh)
   - Successful SSH connection from host
   - Verification commands executed inside VM


2. **Submission Format:**
   - Single PDF file
   - Include name, student ID, and date
   - All screenshots with brief explanation
   - Upload to your portfolio website.



This screenshot shows that the OpenSSH Server is installed on the Ubuntu Server.



This screenshot shows that the SSH service is active and running on the Ubuntu Server.



This screenshot shows the successful remote connection from the client computer to the Ubuntu Server using SSH.

UBUNTU SERVER SSH REMOTE ACCESS LAB

Name: Glen Marquez
Student ID: 2024302231
Course/Year/Section: BSCS 3
Date Submitted:9/3/2026
Instructor: Johneros P. Puyo

1 OBJECTIVES (5 POINTS)
Check all that apply:
✓ **Create and configure a Virtual Machine with Ubuntu Server**
✓ **Configure Bridged Network Adapter for network access**
✓ **Determine and verify the server's IP address**

✓ **Install OpenSSH Server and enable the service**
✓ **Establish successful SSH connection from host machine**
✓ **Execute verification commands to confirm remote access**

2 HARDWARE & SOFTWARE REQUIREMENTS (5 POINTS)

Item	Specification
Host Operating System	Window 11
Virtualization Software (VirtualBox/VMware)	Oracle Vm VirtualBox
Ubuntu Server Version	Ubuntu Server26.04 LTS
VM Name	server143
RAM Allocated	3
Storage Allocated	12
Network Mode	Bridge Adapter
SSH Client Used	Ubuntu Terminal/OpenSSH client

3 VM CONFIGURATION

Setting	Value
VM Name	UBUNTU-SERVER
OS Type	Ubuntu (64-bit)
Memory	4096 MB
Hard Disk	25 GB
Network Adapter	Bridged

4. NETWORK CONFIGURATION
Commands Executed: ip addr
hostname -i
Server IP Address: 169.254.187.31
Network Interface: enp0s3
6. REMOTE CONNECTION
Connection Details:

Parameter	Value

Server IP	169.254.187.31
Username	**marquez**
SSH Port	**22**