










QEMU (Linux-1)

```
ENABLE=yes  
NAME=Ethernet  
IPADDRESS=172.50.0.10  
CIDRLEN=16  
NETWORK=172.50.0.0  
NETMASK=255.255.0.0  
GATEWAY=172.50.0.1  
BROADCAST=172.50.255.255  
DHCP=no
```

```
- /etc/sysconfig/network-scripts/ifcfg-eth0 1/10 10%
```




QEMU (Linux-2)



```
ENABLE=yes
NAME=Ethernet
IPADDRESS=172.50.0.20
CIDRLEN=16
NETWORK=172.50.0.0
NETMASK=255.255.0.0
GATEWAY=172.50.0.1
BROADCAST=172.50.255.255
DHCP=no
```

```
- /etc/sysconfig/network-scripts/ifcfg-eth0 1/10 10%
```



QEMU (DNS)



This PC



Command Prompt

Microsoft Windows [Version 10.0.14393]
(c) 2016 Microsoft Corporation. All rights reserved.

C:\Users\Admin>ipconfig

Windows IP Configuration

Recycle Bin

Ethernet adapter Ethernet:

Connection-specific DNS Suffix . :
Link-local IPv6 Address : fe80::b49b:7e42:b043:9caa%3
IPv4 Address. : 200.12.56.10
Subnet Mask : 255.255.255.0
Default Gateway : 200.12.56.1



Firewall



Google Chrome



Tunnel adapter isatap.{2523F545-554E-448A-9326-684149241DC5}:

Media State : Media disconnected
Connection-specific DNS Suffix . :




God of War



Chrome

C:\Users\Admin>



```
R1
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#interface ethernet0/0
R1(config-if)#ip address 10.0.0.1 255.0.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#interface ethernet0/1
R1(config-if)#ip address 20.0.0.1 255.0.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#
R1(config)#
*Sep 14 13:45:22.617: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#exit
R1#confi
*Sep 14 13:49:52.424: %SYS-5-CONFIG_I: Configured from console by console
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#
R1(config)#ip route 30.0.0.0 255.0.0.0 20.0.0.2
R1(config)#ip route 40.0.0.0 255.0.0.0 20.0.0.2
R1(config)#ip route 172.50.0.0 255.255.0.0 20.0.0.2
R1(config)#ip route 200.12.56.0 255.255.255.0 20.0.0.2
R1(config)#exit
R1#
```

```
R1#
*Sep 14 13:51:01.931: %SYS-5-CONFIG_I: Configured from console by console
R1#
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#access-list 10 permit 10.0.0.0 0.0.0.0
R1(config)#access-list 10 permit 10.0.0.10 0.0.0.0
R1(config)#
R1(config)#interface ethernet0/0
R1(config-if)#ip access-group 10 in
R1(config-if)#
R1(config-if)#exit
R1(config)#exit
R1#
R1#
R1#
*Sep 14 14:20:53.949: %SYS-5-CONFIG_I: Configured from console by console
R1#show access-list
Standard IP access list 10
    20 permit 10.0.0.10 (17 matches)
    10 permit 10.0.0.0
R1#
R1#
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#access-list 10 permit 10.0.0.20 0.0.0.0
R1(config)#exit
R1#
R1#
R1#sh
*Sep 14 14:37:51.046: %SYS-5-CONFIG_I: Configured from console by console
R1#show access-list
Standard IP access list 10
    20 permit 10.0.0.10 (49 matches)
    10 permit 10.0.0.0
    30 permit 10.0.0.20
R1#
```

```
R1#
R1#
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#$ 100 permit tcp 10.0.0.10 0.0.0.0 172.50.0.10 0.0.0.0 eq 80
R1(config)#$ 100 permit tcp 10.0.0.20 0.0.0.0 172.50.0.20 0.0.0.0 eq 80
R1(config)#
R1(config)#interface ethernet 0/0
R1(config-if)#ip access-group 10 in
R1(config-if)#exit
R1(config)#
R1(config)#
R1(config)#exit
R1#
R1#
*Sep 14 14:46:23.875: %SYS-5-CONFIG_I: Configured from console by console
R1#show access-list
Standard IP access list 10
  20 permit 10.0.0.10 (56 matches)
  10 permit 10.0.0.0
  30 permit 10.0.0.20 (35 matches)
Extended IP access list 100
  10 permit tcp host 10.0.0.10 host 172.50.0.10 eq www
  20 permit tcp host 10.0.0.20 host 172.50.0.20 eq www
R1#
R1#
```

```
R1#
R1#
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#access-list 10 deny 10.0.0.0 0.0.0.0
R1(config)#exit
R1#
R1#sh
*Sep 14 14:51:33.028: %SYS-5-CONFIG_I: Configured from console by console
R1#show access list
% Ambiguous command: "show access list"
R1#show access-list
Standard IP access list 10
 20 permit 10.0.0.10 (174 matches)
 10 permit 10.0.0.0
 40 deny 10.0.0.0
 30 permit 10.0.0.20 (35 matches)
Extended IP access list 100
 10 permit tcp host 10.0.0.10 host 172.50.0.10 eq www
 20 permit tcp host 10.0.0.20 host 172.50.0.20 eq www
R1#
```

```
R1
R1(config)# 100 permit udp 10.0.0.0 0.255.255.255 200.12.56.10 0.0.0.0 eq 53
R1(config)#exit
R1#
R1#
*Sep 14 15:13:15.403: %SYS-5-CONFIG_I: Configured from console by console
R1#show access-list
Standard IP access list 10
  20 permit 10.0.0.10 (242 matches)
  10 permit 10.0.0.0
  40 deny 10.0.0.0
  30 permit 10.0.0.20 (35 matches)
Extended IP access list 100
  10 permit tcp host 10.0.0.10 host 172.50.0.10 eq www
  20 permit tcp host 10.0.0.20 host 172.50.0.20 eq www
  30 permit udp 10.0.0.0 0.255.255.255 host 200.12.56.10 eq domain
R1#
R1#
```

```
R1#
R1#
R1#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#
R1(config)# 100 permit icmp 10.0.0.0 0.255.255.255 172.50.0.0 0.0.255.255
R1(config)#
R1(config)# 100 permit ip 10.0.0.0 0.255.255.255 172.50.0.0 0.0.255.255
R1(config)#exit
R1#
R1#
R1#
*Sep 14 15:38:03.497: %SYS-5-CONFIG_I: Configured from console by console
R1#show access-list
Standard IP access list 10
  20 permit 10.0.0.10 (534 matches)
  10 permit 10.0.0.0
  40 deny 10.0.0.0
  30 permit 10.0.0.20 (35 matches)
Extended IP access list 100
  10 permit tcp host 10.0.0.10 host 172.50.0.10 eq www
  20 permit tcp host 10.0.0.20 host 172.50.0.20 eq www
  30 permit udp 10.0.0.0 0.255.255.255 host 200.12.56.10 eq domain
  40 permit icmp 10.0.0.0 0.255.255.255 172.50.0.0 0.0.255.255
  50 permit ip 10.0.0.0 0.255.255.255 172.50.0.0 0.0.255.255
R1#
--
```

