




```
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#
R1(config)#
R1(config)#interface ethernet0/0
R1(config-if)#ip address 10.0.0.1 255.0.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#interface ethernet0/1
R1(config-if)#ip address 20.0.0.1 255.0.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#
*Sep 27 17:40:07.036: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1(config)#router rip
R1(config-router)#network 10.0.0.0
R1(config-router)#network 20.0.0.0
R1(config-router)#exit
R1(config)#
R1(config)#exit
R1#
*Sep 27 17:43:13.452: %SYS-5-CONFIG_I: Configured from console by console
R1#
```

```
R2
R2#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
R2(config)#
R2(config)#
R2(config)#interface ethernet 0/0
R2(config-if)#ip address 20.0.0.2 255.0.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#interface ethernet 0/1
R2(config-if)#ip address 30.0.0.1 255.0.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#
*Sep 27 17:40:02.301: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2(config)#router rip
R2(config-router)#network 20.0.0.0
R2(config-router)#network 30.0.0.0
R2(config-router)#exit
R2(config)#exit
R2#
*Sep 27 17:43:49.960: %SYS-5-CONFIG_I: Configured from console by console
R2#
```

```
R3#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#
R3(config)#
R3(config)#interface ethernet 0/1
R3(config-if)#ip address 30.0.0.2 255.0.0.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#
R3(config)#
R3(config)#interface ethernet 0/0
R3(config-if)#ip address 40.0.0.1 255.0.0.0
R3(config-if)#
*Sep 27 17:40:12.415: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#
R3(config)#
R3(config)#router rip
R3(config-router)#network 30.0.0.0
R3(config-router)#network 40.0.0.0
R3(config-router)#exit
R3(config)#exit
R3#
*Sep 27 17:44:20.140: %SYS-5-CONFIG_I: Configured from console by console
R3#
```

R1#

R1#

R1#

R1#show ip route

Codes: L - local, C - connected, S - static, R - RIP, M - mobile, B - BGP
D - EIGRP, EX - EIGRP external, O - OSPF, IA - OSPF inter area
N1 - OSPF NSSA external type 1, N2 - OSPF NSSA external type 2
E1 - OSPF external type 1, E2 - OSPF external type 2
i - IS-IS, su - IS-IS summary, L1 - IS-IS level-1, L2 - IS-IS level-2
ia - IS-IS inter area, * - candidate default, U - per-user static route
o - ODR, P - periodic downloaded static route, H - NHRP, l - LISP
a - application route
+ - replicated route, % - next hop override, p - overrides from PfR

Gateway of last resort is not set

10.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 10.0.0.0/8 is directly connected, Ethernet0/0
L 10.0.0.1/32 is directly connected, Ethernet0/0
20.0.0.0/8 is variably subnetted, 2 subnets, 2 masks
C 20.0.0.0/8 is directly connected, Ethernet0/1
L 20.0.0.1/32 is directly connected, Ethernet0/1
R 30.0.0.0/8 [120/1] via 20.0.0.2, 00:00:12, Ethernet0/1
R 40.0.0.0/8 [120/2] via 20.0.0.2, 00:00:12, Ethernet0/1

R1#

R1#

R1#

