




```
R1#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#interface ethernet0/0
R1(config-if)#ip address 50.0.0.1 255.0.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#interface ethernet0/1
R1(config-if)#ip address 172.16.0.1 255.255.0.0
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#exit
R1#
*Sep  1 05:25:39.512: %SYS-5-CONFIG_I: Configured from console by console
R1#
*Sep  1 05:26:57.570: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R1#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#ip route 192.168.2.0 255.255.255.0 172.16.0.2
R1(config)#exit
R1#
```

```
R2#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#interface ethernet0/1
R2(config-if)#ip address 172.16.0.2 255.255.0.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#interface ethernet0/0
R2(config-if)#ip address 192
*Sep  1 05:27:02.001: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2(config-if)#ip address 192.168.2.1 255.255.255.0
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#exit
R2#
*Sep  1 05:27:41.427: %SYS-5-CONFIG_I: Configured from console by console
R2#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#ip route 50.0.0.0 255.0.0.0 172.16.0.1
R2(config)#exit
R2#
```

```
R2#configure terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#interface ethernet0/0
R2(config-if)#ip helper-address 172.16.0.1
R2(config-if)#exit
R2(config)#
```

```
R1
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.0.0 255.0.0.0
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#ip dhcp excluded-address 50.0.0.1 50.0.0.50
R1(config)#exit
R1#
R1#
R1#
R1#
*Sep  1 05:42:11.159: %SYS-5-CONFIG_I: Configured from console by console
R1#show ip dhcp binding
Bindings from all pools not associated with VRF:
IP address          Client-ID/
                   Hardware address/
                   User name
50.0.0.51           0100.5079.6668.07   Sep 02 2026 01:15 PM   Automatic
R1#configure terminal
Enter configuration commands, one per line. End with CNTL/Z.
R1(config)#ip dhcp pool SALES
R1(dhcp-config)#network 192.168.2.0 255.255.255.0
R1(dhcp-config)#default-router 192.168.2.1
R1(dhcp-config)#dns-server 8.8.8.8
R1(dhcp-config)#lease 1 2 3
R1(dhcp-config)#exit
R1(config)#
R1(config)#ip dhcp excluded-address 192.168.2.1 192.168.2.50
R1(config)#exit
```

```
VPC-1
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-1> ip dhcp
DDD
Can't find dhcp server

VPC-1> ip dhcp
DDORA IP 50.0.0.51/8 GW 50.0.0.1
```

