





```
HO-EDGE#show ip int br
Interface                               IP-Address    OK? Method Status    Prot
-----                               -
Loopback0                               10.0.0.1      YES TFTP   up        up
Ethernet0/0                             10.0.0.1      YES TFTP   up        up
Ethernet0/1                             20.0.0.1      YES TFTP   up        up
Ethernet0/2                             unassigned    YES TFTP   down      down
Ethernet0/3                             unassigned    YES TFTP   down      down

HO-EDGE#
HO-EDGE#
HO-EDGE#config terminal
Enter configuration commands, one per line. End with CNTL/Z.
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
HO-EDGE(config)#
HO-EDGE(config)#no logging console
HO-EDGE(config)#
HO-EDGE(config)#int tunnel 1
HO-EDGE(config-if)#ip add 1.0.0.1 255.0.0.0
HO-EDGE(config-if)#tunnel source 20.0.0.1
HO-EDGE(config-if)#tunnel destination 30.0.0.2
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#ip route 192.168.1.0 255.255.255.0 tunnel 1
HO-EDGE(config)#
HO-EDGE(config)#exit
HO-EDGE#
```

```
DC-EDGE
DC-EDGE#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
DC-EDGE(config)#
DC-EDGE(config)#ip route 0.0.0.0
*Sep 27 13:22:05.180: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#
DC-EDGE(config)#int tunnel 1
DC-EDGE(config-if)#ip a
*Sep 27 13:22:55.976: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnell, changed state to down
DC-EDGE(config-if)#ip add 1.0.0.2 255.0.0.0
DC-EDGE(config-if)#tunnel source 30.0.0.2
DC-EDGE(config-if)#tunnel destination 20.0.0.1
DC-EDGE(config-if)#exit
*Sep 27 13:23:33.708: %LINEPROTO-5-UPDOWN: Line protocol on Interface Tunnell, changed state to up
DC-EDGE(config-if)#exit
DC-EDGE(config)#
DC-EDGE(config)#ip route 10.0.0.0 255.0.0.0 tunnel 1
DC-EDGE(config)#
DC-EDGE(config)#exit
DC-EDGE#
*Sep 27 13:24:28.153: %SYS-5-CONFIG_I: Configured from console by console
DC-EDGE#
```



The image shows a terminal window titled "QEMU (Linux-1)". The window has a standard Linux desktop environment with various icons in the top bar, including a cube, a window, a gear, a refresh symbol, a Windows logo, a terminal icon, an information icon, a close button, and a download icon. The terminal output displays the following network configuration:

```
ENABLE=yes  
NAME=Ethernet  
IPADDRESS=192.168.1.10  
CIDRLEN=24  
NETWORK=192.168.1.0  
NETMASK=255.255.255.0  
GATEWAY=192.168.1.1  
BROADCAST=192.168.1.255  
DHCP=no
```

```
QEMU (Linux-1)
service network restart
/ifcfg-eth0: line 10: :wq: command not found
etc/sysconfig/network-scripts/ifcfg-eth0: line 10: :wq: command not found
removing default gateway for Ethernet interface ..... [ OK ]
shutting down Ethernet interface eth0 ..... [ OK ]
shutting down loopback interface lo ..... [ OK ]
bringing up loopback interface lo ..... [ OK ]
/ifcfg-eth0: line 10: :wq: command not found
etc/sysconfig/network-scripts/ifcfg-eth0: line 10: :wq: command not found
bringing up Ethernet interface eth0 ..... [ OK ]
set up default gateway ..... [ OK ]
```

 QEMU (Linux-2)



```
ENABLE=yes  
NAME=Ethernet  
IPADDRESS=192.168.1.20  
CIDRLEN=24  
NETWORK=192.168.1.0  
NETMASK=255.255.255.0  
GATEWAY=192.168.1.1  
BROADCAST=192.168.1.255  
DHCP=no
```

```
QEMU (Linux-2)
service network restart
Removing default gateway for Ethernet interface ..... [ OK ]
shutting down Ethernet interface eth0 ..... [ OK ]
shutting down loopback interface lo ..... [ OK ]
bringing up loopback interface lo ..... [ OK ]
bringing up Ethernet interface eth0 ..... [ OK ]
set up default gateway ..... [ OK ]
```

