


SUBNETTING



```
R1#
*Sep 11 05:14:41.620: %SYS-5-CONFIG_I: Configured from console by console
R1#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R1(config)#interface ethernet0/0
R1(config-if)#ip address 50.0.1.129 255.255.255.192
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#
R1(config)#interface ethernet0/1
R1(config-if)#ip address 50.0.1.193 255.255.255.252
R1(config-if)#no shutdown
R1(config-if)#exit
R1(config)#
R1(config)#
R1(config)#ip route 50.0.0.0 255.255.255.0 50.0.1.194
R1(config)#ip route 50.0.1.196.255.255.255.252 50.0.1.194
      ^
% Invalid input detected at '^' marker.

R1(config)#ip route 50.0.1.196 255.255.255.252 50.0.1.194
R1(config)#ip route 50.0.1.0 255.255.255.128 50.0.1.194
R1(config)#exit
```

```
R2
R2(config)#
R2(config)#interface ethernet
*Sep 11 05:17:31.536: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R2(config)#interface ethernet0/0
R2(config-if)#ip address 50.0.1.1 255.255.255.128
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#interface ethernet0/1
R2(config-if)#ip address 50.0.1.194 255.255.255.252
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#interface ethernet0/2
R2(config-if)#ip address 50.0.1.197 255.255.255.252
R2(config-if)#no shutdown
R2(config-if)#exit
R2(config)#
R2(config)#
R2(config)#ip route 50.0.1.128 255.255.255.192 50.0.1.193
R2(config)#ip route 50.0.0.0 255.255.255.0 50.0.1.198
R2(config)#exit
R2#
```


R3

```
R3#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R3(config)#
R3(config)#
R3(config)#interface ethernet0/1
R3(config-if)#ip address 50.0.1.198 255.255.255.252
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#
R3(config)#interface ethernet0/0
R3(config-if)#ip address 50.0.0.1 255.255.255.0
R3(config-if)#no shutdown
R3(config-if)#exit
R3(config)#
*Sep 11 05:24:24.687: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
R3(config)#ip route 50.0.1.128 255.255.255.192 50.0.1.197
R3(config)#ip route 50.0.1.0 255.255.255.128 50.0.1.197
R3(config)#ip route 50.0.1.192 255.255.255.252 50.0.1.197
R3(config)#exit
R3#
```

```
R1
R1(config)#
R1(config)#ip dhcp pool HR
R1(dhcp-config)#network 50.0.1.128 255.255.255.192
R1(dhcp-config)#default-router 50.0.1.129
R1(dhcp-config)#exit
R1(config)#
R1(config)#ip dhcp pool PRO
R1(dhcp-config)#network 50.0.1.0 255.255.255.128
R1(dhcp-config)#default-router 50.0.1.1
R1(dhcp-config)#exit
R1(config)#
R1(config)#ip dhcp pool SALES
R1(dhcp-config)#network 50.0.0.0 255.255.255.0
R1(dhcp-config)#default-router 50.0.0.1
R1(dhcp-config)#exit
R1(config)#
*Sep 11 05:54:00.362: %DHCPD-4-PING_CONFLICT: DHCP address conflict: server pinged 50.0.1.1.
R1(config)#
*Sep 11 05:54:47.232: %DHCPD-4-PING_CONFLICT: DHCP address conflict: server pinged 50.0.0.1.
R1(config)#
R1(config)#
R1(config)#
```

```
R2#config terminal
Enter configuration commands, one per line.  End with CNTL/Z.
R2(config)#
R2(config)#
R2(config)#interface ethernet0/0
R2(config-if)#ip helper-address 50.0.1.193
R2(config-if)#exit
R2(config)#
```

```
R3#  
R3#config terminal  
Enter configuration commands, one per line.  End with CNTL/Z.  
R3(config)#  
R3(config)#interface ethernet0/0  
R3(config-if)#ip helper-address 50.0.1.193  
R3(config-if)#exit  
R3(config)#
```



```
VPC-1
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.


Executing the startup file

VPC-1> ip dhcp
DDORA IP 50.0.0.1/26 GW 50.0.0.129

VPC-1> ping 50.0.0.1

84 bytes from 50.0.0.1 icmp_seq=1 ttl=253 time=1.193 ms
84 bytes from 50.0.0.1 icmp_seq=2 ttl=253 time=1.713 ms
84 bytes from 50.0.0.1 icmp_seq=3 ttl=253 time=1.638 ms
84 bytes from 50.0.0.1 icmp_seq=4 ttl=253 time=1.209 ms
84 bytes from 50.0.0.1 icmp_seq=5 ttl=253 time=1.876 ms

VPC-1>
```



VPC-2

Executing the startup file

VPC-2> ip dhcp

DDORA IP 50.0.1.3/25 GW 50.0.1.1


VPC-2> ping 50.0.0.1

84 bytes from 50.0.0.1 icmp_seq=1 ttl=254 time=0.799 ms
84 bytes from 50.0.0.1 icmp_seq=2 ttl=254 time=1.158 ms
84 bytes from 50.0.0.1 icmp_seq=3 ttl=254 time=1.780 ms
84 bytes from 50.0.0.1 icmp_seq=4 ttl=254 time=1.460 ms
84 bytes from 50.0.0.1 icmp_seq=5 ttl=254 time=1.031 ms

VPC-2> ping 50.0.1.129

84 bytes from 50.0.1.129 icmp_seq=1 ttl=254 time=1.348 ms
84 bytes from 50.0.1.129 icmp_seq=2 ttl=254 time=1.237 ms
84 bytes from 50.0.1.129 icmp_seq=3 ttl=254 time=1.025 ms
84 bytes from 50.0.1.129 icmp_seq=4 ttl=254 time=0.847 ms
84 bytes from 50.0.1.129 icmp_seq=5 ttl=254 time=1.066 ms

VPC-2> █



```
VPC-3
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC-3> ip dhcp
DDORA IP 50.0.0.3/24 GW 50.0.0.1

VPC-3> ping 50.0.1.129

84 bytes from 50.0.1.129 icmp_seq=1 ttl=253 time=1.101 ms
84 bytes from 50.0.1.129 icmp_seq=2 ttl=253 time=1.898 ms
84 bytes from 50.0.1.129 icmp_seq=3 ttl=253 time=1.455 ms
84 bytes from 50.0.1.129 icmp_seq=4 ttl=253 time=1.633 ms
84 bytes from 50.0.1.129 icmp_seq=5 ttl=253 time=1.943 ms

VPC-3> 
```

SUBNETTING

