

Solipsis

Installation Guide

System configuration

Minimal system configuration

- 1Gb of physical memory
- 250 Mb of free disk space
- Windows® XP or Vista
- DirectX® 9.0 or OpenGL® 2 compatible graphic card with 128Mb memory
- Internet connection

Recommended system configuration


- 2Gb of physical memory
- 250 Mb of free disk space
- Windows® XP or Vista
- DirectX® 9.0 or OpenGL® 2 compatible graphic card with 512Mb memory
- Internet connection

Installation




CD/DVD installation : Insert the disk


Network installation : Open the Windows® explorer and reach the installation directory

Run the Setup program Solipsis-x.y.z-win32.exe and follow instructions




During installation you will be prompted to install required third-parties components : Ms Visual C++ redistributable, Python, DirectX and Ageia PhysX packages. Install them if they are not yet present on your computer.





Applications launch

Start menu and Desktop icons




Navigator is the front-end, you will use it to navigate into Solipsis worlds.

RakNet Servers are, for instance, main site nodes describing different worlds. By default, 3 worlds are available : the Children Island, the Delta Station and the city of Rennes.

The **Worlds Server** is an helper server registering known Solipsis worlds managed by their respective RakNet Servers.

If you want to serve worlds yourself, launch the **Worlds Server** and **RakNet Servers** of worlds you will visit, for example the Children Island



The image contains two screenshots of console windows. The top window is titled 'Solipsis Worlds Server' and shows the process of loading users from a file, starting the server on localhost:8550, and displaying a simple menu with 'u/U' for 'Users' and 'q/Q' for 'Quit'. The bottom window is titled 'Solipsis RakNet Server (Children Island)' and shows a detailed log of the RakNet server initialization, including file loading and node registration.

```
Solipsis Worlds Server
Loading Users from users.xml
Starting Worlds server on localhost:8550
Press CTRL+C or CTRL+PAUSE to stop
Starting console
=====
=                C O N S O L E                =
=====
u/U ..... Users
q/Q ..... Quit

-


Solipsis RakNet Server (Children Island)
11:16:23: Starting RakNet server
11:16:23: ConsoleThread>BasicThread::start()
11:16:23: RakNetServer::initialize()
11:16:23: ConsoleThread>BasicThread::startRoutine() calling run()
11:16:23: ConsoleThread::run()
11:16:23: RakNetServer::initialize() Server started on 192.168.104.20:8559
11:16:23: CacheManager::initialize() loading cache from C:\Program Files\Solipsis\Media\cacheServerIsland\cache.xml
11:16:23: RakNetServer::loadNodeIdFile() loading node with nodeId:11112223 from C:\Program Files\Solipsis\Media\cacheServerIsland\11112223.xml
11:16:23: RakNetEntity::addFilesInCacheManager()
11:16:23: RakNetEntity::addFilesInCacheManager() adding file 11112223.ssf
11:16:23: RakNetSiteNode::RakNetSiteNode()
11:16:23: RakNetServer::initialize() scene nodeId:11112223 loaded
11:16:23: RakNetServer::run()

-
```

... next step, in the **Navigator** options panel you will have to change the Worlds Server address to point to your own **Worlds Server**.

If you simply want to connect to existing worlds on other servers then you have just to launch the **Navigator**.


On first launch you will have to choose your rendering configuration




On login panel, click on the **World** button,



select the world, you will return to the login panel,




go to the **Options** panel to choose the authentication type, by default the Worlds Server will give you 1 unique identifier according to your login, press **Ok** and return to the login panel,



Nota : you can choose to use your Facebook account, then you will be redirected on the Facebook authentication page on your external web browser to log on the Solipsis external application.

Enter your login/password (choose a password if you are a new user) and press **Connect**, after the authentication process you should return to the login panel, press **Connect** again to enter into the world.



Solipsis - Installation Guide - v1.0