

Solipsis

Installation Guide

1. System configuration

Minimal system configuration

- 1Gb of physical memory
- 250 Mb of free disk space
- Windows® XP or Vista
- DirectX® 9.0 or OpenGL® 2 compatible graphic card with 128Mb memory
- Internet connection

Recommended system configuration

- 2Gb of physical memory
- 250 Mb of free disk space
- Windows® XP or Vista
- DirectX® 9.0 or OpenGL® 2 compatible graphic card with 512Mb memory
- Internet connection

2. Installation

CD/DVD installation : Insert the disk

Network installation :


1/ Open the Windows® explorer

2/ Reach the installation directory

Run the Setup program Solipsis-x.y.z-win32.exe

Follow instructions










During installation you will be prompted to install required third-parties components :

- Ms Visual C++ redistributable
- Python
- DirectX
- Ageia PhysX packages

Install them if they are not yet present on your computer.








3. Applications launch

Start menu and Desktop icons



Navigator is the front-end. You will use it to navigate into Solipsis worlds.

RakNet Servers are, for instance, main site nodes describing different worlds.

By default, 3 worlds are available : the Children Island, the Delta Station and the city of Rennes.


The **Worlds Server** is an helper server which registers known Solipsis worlds managed by their respective RakNet Servers.

You may want to serve worlds yourself, see the specific note **A** below, or to connect to existing worlds on other servers then go directly to note **B**.

A. If you want to serve worlds yourself

1/ Launch the **Worlds Server**

2/ Launch **RakNet Servers** of worlds you will visit, for example the Children Island




3/ In the **Navigator** options panel, change the **Worlds Server** address to point to your own **Worlds Server**.

B. Connect to worlds

1/ Launch the **Navigator**

On first launch you have to choose your rendering configuration, press OK to choose default parameters



2/ You reach the login panel


B.1/ How to choose the world you want

1/ You are on the login panel

2/ Click on the **World** button



3/ Select the world




4/ You return to the login panel

B.2/ How to log in

1/ You are on the login panel

1/ Click on **Options** to reach the Options panel to choose the authentication type

By default the Worlds Server will give you 1 unique identifier according to your login/password



Nota : you can choose to use your Facebook account, then you will be redirected on the Facebook authentication page on your external web browser to log on the Solipsis external application.

2/ Press **Ok** to return to the login panel

3/ Enter your login/password (choose a password if you are a new user)

4/ Press **Connect**

5/ If the authentication process succeeded you directly enter into the world.

