

Solipsis

Installation Guide

1. System configuration

Minimal system configuration

- 1Gb of physical memory
- 250 Mb of free disk space
- Windows® XP or Vista
- DirectX® 9.0 or OpenGL® 2 compatible graphic card with 128Mb memory
- Internet connection

Recommended system configuration

- 2Gb of physical memory
- 250 Mb of free disk space
- Windows® XP or Vista
- DirectX® 9.0 or OpenGL® 2 compatible graphic card with 512Mb memory
- Internet connection

2. Installation

CD/DVD installation : Insert the disk


Network installation :

1/ Open the Windows® explorer

2/ Reach the installation directory

Run the Setup program Solipsis-x.y.z-win32.exe




Follow instructions




During installation you will be prompted to install required third-parties components :

- Ms Visual C++ redistributable
- Python
- DirectX
- Ageia PhysX packages


Install them if they are not yet present on your computer.





3. Applications launch

Start menu and Desktop icons



Navigator is the front-end. You will use it to navigate into Solipsis worlds.

RakNet Servers are, for instance, main site nodes describing different worlds.


By default, 3 worlds are available : the Children Island, the Delta Station and the city of Rennes.

The **Worlds Server** is an helper server which registers known Solipsis worlds managed by their respective RakNet Servers.

You may want to serve worlds yourself, see the specific note **A** below, or to connect to existing worlds on other servers then go directly to note **B**.

A. If you want to serve worlds yourself

- 1/ Launch the **Worlds Server**
- 2/ Launch **RakNet Servers** of worlds you will visit, for example the Children Island



The image shows two separate command-line windows. The top window, titled 'Solipsis Worlds Server', displays the process of starting a worlds server on localhost:8550. It includes instructions to press CTRL+C or CTRL+PAUSE to stop and shows a console menu with options 'u/U' for Users and 'q/Q' for Quit. The bottom window, titled 'Solipsis RakNet Server (Children Island)', shows a detailed log of the RakNet server initialization. The log includes timestamps (11:16:23) and messages for starting the server, initializing threads, loading cache files, and loading a specific node (11112223) from a file.

```
C:\> Solipsis Worlds Server

Loading Users from users.xml
Starting Worlds server on localhost:8550
Press CTRL+C or CTRL+PAUSE to stop
Starting console
=====
=                               C O N S O L E                               =
=====
u/U ..... Users
q/Q ..... Quit

-

C:\> Solipsis RakNet Server (Children Island)

11:16:23: Starting RakNet server
11:16:23: ConsoleThread>BasicThread::start()
11:16:23: RakNetServer::initialize()
11:16:23: ConsoleThread>BasicThread::startRoutine() calling run()
11:16:23: ConsoleThread::run()
11:16:23: RakNetServer::initialize() Server started on 192.168.104.20:8559
11:16:23: CacheManager::initialize() loading cache from C:\Program Files\Solipsis\Media\cacheServerIsland\cache.xml
11:16:23: RakNetServer::loadNodeIdFile() loading node with nodeId:11112223 from C:\Program Files\Solipsis\Media\cacheServerIsland\11112223.xml
11:16:23: RakNetEntity::addFilesInCacheManager()
11:16:23: RakNetEntity::addFilesInCacheManager() adding file 11112223.ssf
11:16:23: RakNetSiteNode::RakNetSiteNode()
11:16:23: RakNetServer::initialize() scene nodeId:11112223 loaded
11:16:23: RakNetServer::run()


-
```

- 3/ In the **Navigator** options panel, change the **Worlds Server** address to point to your own **Worlds Server**.

B. Connect to worlds

1/ Launch the Navigator

On first launch you have to choose your rendering configuration, Direct3D9 is the most commonly used, choose it if you are not




2/ Press **Ok** to reach the login panel

B.1/ How to choose the world you want

- 1/ You are on the login panel
- 2/ Click on the **World** button




- 3/ Select the world



- 4/ Press **Ok** to return to the login panel

B.2/ How to log in

- 1/ You are on the login panel
- 2/ Click on **Options** to reach the Options panel to choose the authentication type
By default the Worlds Server will give you 1 unique identifier according to your login/password



Nota : you can choose to use your Facebook account, then you will be redirected on the Facebook authentication page on your external web browser to log on the Solipsis external application.

- 3/ Press **Ok** to return to the login panel
- 4/ Enter your login/password (choose a password if you are a new user)
- 5/ Press **Connect**
- 6/ If the authentication process succeeded you directly enter into the world.

