Requirement	No.	TestName	Purpose	Input	Input Files	Output	Output Files
			Transaction S	Summary File			
Each line at most 61 characters	R1T1	TransLen	Check if each line is at most 61 characters	logout	transaction message(length > 61)	Error prompt for exceeding length	None
	R1T2	TransLen2	Check if each line is at most 61 characters	logout	transaction message(length <=61)	None	None
Trans Code always the first three	R2T1	TransCode	Check if transCode is the first three	logout	DEP 123456 100000000 0000 ***	None	None
	R2T2	TransCode2	Check if transCode is the first three	logout	132 DEP456 100000000 0000 ***	Error prompt for trans code	None
	R2T3	TransCode3	check if transCode is the first three	logout	996 123456 100000000 DEPO ***	Error prompt for trans code	None
Items are separated by one space	R3T1	TransItem	Check if there is only one space between item	logout	DEP 123456 100000000 000 ***	None	None
	R3T2	TransItem2	Check if there is only one space between item	logout	DEP123456 100000000 000 ***	Error prompt for spacing	None
	R3T3	TransItem3	Check if there is only one space between item	logout	DEP123456 100000000 000***	Error prompt for spacing	None
	R3T4	TransItem4	Check if there is only one space between item	logout	DEP123456100 000000000***	Error prompt for spacing	None
	R4T1	TransAcc	Check if number is seven digits and not begin with 0	logout	DEP 123456 100000000 000 ***	Error prompt for invalid account	None

Account number 7 digists and not begin with zero	R4T2	TransAcc2	Check if number is seven digits and not begin with 0	logout	DEP 1000000000 100000000 000 ***	Error prompt for invalid account	None
	R4T3	TransAcc3	Check if number is seven digits and not begin with 0	logout	DEP 1234567 100000000 000 ***	None	None
	R4T4	TransAcc4	Check if number is seven digits and not begin with 0	logout	DEP ar12345 100000000 000 ***	Error prompt for invalid account	None
	R4T5	TransAcc5	Check if number is seven digits and not begin with 0	logout	DEP aasdliajsoi 100000000 000 ***	Error prompt for invalid account	None
Monetary btw with 3 and 8 digits	R5T1	TransMon	Check if monetary begin with 3 and 8 digits	logout	DEP 1234567 asd 000 ***	Error prompt for invalid monetary	None
	R5T2	TransMon2	Check if monetary begin with 3 and 8 digits	logout	DEP 1234567 12 000 ***	Error prompt for invalid monetary	None
	R5T3	TransMon3	Check if monetary begin with 3 and 8 digits	logout	DEP 1234567 1000000000 000 ***	Error prompt for invalid monetary	None
	R5T4	TransMon4	Check if monetary begin with 3 and 8 digits	logout	DEP 1234567 1234567 000 ***	None	None

	R5T5	TransMon5	Check if monetary begin with 3 and 8 digits	logout	DEP 1234567 1234 000 ***	None	None
Account Name between 3 and 30 charactersInclu ding spaces but not begin or end with space	R6T1	TransAccName	Check transaction account name	logout	DEP 1234567 1234 000 zzl	None	None
	R6T2	TransAccName 2	Check transaction account name	logout	DEP 1234567 1234 000 a o q ei as	None	None
	R6T3	TransAccName 3	Check transaction account name	logout	DEP 1234567 1234 000 alfihaslrguohasr okg	Error prompt for invalid account name	None
	R6T4	TransAccName 4	Check transaction account name	logout	DEP 1234567 1234 000 alfihaslrguohasr okg	Error prompt for invalid account name	None
	R6T5	TransAccName 5	Check transaction account name	logout	DEP 1234567 1234 000 alfihaslrguohasr okg	Error prompt for invalid account name	None
Unused are filled with zeroes	R7T1	TransUnused	Check unused	createacct	createacct	Account created	Transaction summary
				logout	NEW 0000000 0000 000 zzl	None	None
	R7T2	TransUnused2	Check unused	createacct	createacct	Account created	Transaction summary
				logout	NEW 1234567 1111 000 zzl	Error prompt for invalid trans file	None
	R8T1	TransUnusedNa me	Check unused Name	transfer	account1, 2000, account2	Transffered 2000 to account2	Transaction summary

Unused name filled with ***				logout	XFR 1234567 1111 7654321 ***	None	None
	R8T2	TransUnusedNa me2	Check unused Name	transfer	account1, 2000, account2	Transffered 2000 to account2	Transaction summary
				logout	XFR 1234567 1111 7654321 qwe	Error prompt for invalid trans file	None
EOS at end of file	R9T1	TransEOS	Check EOS at last	logout	EOS	None	None
	R9T2	TransEOS2	Check EOS at last	logout	abc	Error prompt for invalid trans file	None