asuG25


Interface
ZIF_GW_METHODS
Implemented / Active
Proper...
Interfaces
Attributes
Metho...
Events
Types
Aliases
Parameter
Exception
Method
Level
M...
Description
CREATE_ENTITY
Static Method
CREATE_DEEP_ENTITY
Static Method
DELETE_ENTITY
Static Method
GET_ENTITY
Static Method
GET_ENTITYSET
Static Method
UPDATE_ENTITY
Static Method
EXECUTE_ACTION
Static Method

COMMON INTERFACE


Interface
ZIF_GW_METHODS
Implemented / Active
Proper...
Interfaces
Attributes
Metho...
Events
Types
Aliases
Method parameters
GET_ENTITYSET
Methods
Exceptions
Parameter
Type
P...
O...
Typing Method
Associated Type
IV_ENTITY_NAME Importing Type STRING
IV_ENTITY_SET_NAME Importing Type STRING
IV_SOURCE_NAME Importing Type STRING
IT_FILTER_SELECT_OPTIONS Importing Type /IWBEP/T_MGW_SELECT_OPTION
IS_PAGING Importing Type /IWBEP/S_MGW_PAGING
IT_KEY_TAB Importing Type /IWBEP/T_MGW_NAME_VALUE_PAIR
IV_NAVIGATION_PATH Importing Type /IWBEP/T_MGW_NAVIGATION_PATH
IT_ORDER Importing Type /IWBEP/T_MGW_SORTING_ORDER
IV_FILTER_STRING Importing Type STRING
IV_SEARCH_STRING Importing Type STRING
IO_TECH_REQUEST_CONTEXT Importing Type Ref To /IWBEP/IF_MGW_REQ_ENTITYSET
IO_MODEL Importing Type Ref To /CL_GW_MODEL
IO_MESSAGE_CONTAINER Importing Type Ref To /IWBEP/IF_MESSAGE_CONTAINER
ET_ENTITYSET Exporting Type DATA
ES_RESPONSE_CONTEXT Exporting Type /IWBEP/IF_MGW_APPL_SRV_RUNTIME=>TY_S_MGW_RESPONSE_CONTEXT

Model



Message Container

Untyped data object

COMMON INTERFACE



Model

Message Container

Untyped data object

ZCL_GW_MODEL



Method	Level	Visibility	M...	Description
CONSTRUCTOR	Instance	Public		CONSTRUCTOR
GET_ABAP_FIELD_NAME	Instance	Public		
GET_SORTABLE_ABAP_FIELD_NAME	Instance	Public		
GET_FILTERABLE_ABAP_FIELD_NAME	Instance	Public		
GET_ENTITY_PROPERTIES	Instance	Private		
GET_PROPERTY	Instance	Private		