
# Normalização



https://arxiv.org/pdf/1803.08494.pdf

## **Batch Norm**

**Input:** Values of x over a mini-batch:  $\mathcal{B} = \{x_{1...m}\}$ ;

Parameters to be learned:  $\gamma$ ,  $\beta$ 

Output:  $\{y_i = BN_{\gamma,\beta}(x_i)\}$ 

$$\mu_{\mathcal{B}} \leftarrow \frac{1}{m} \sum_{i=1}^{m} x_{i} \qquad // \text{ mini-batch mean}$$
 
$$\sigma_{\mathcal{B}}^{2} \leftarrow \frac{1}{m} \sum_{i=1}^{m} (x_{i} - \mu_{\mathcal{B}})^{2} \qquad // \text{ mini-batch variance}$$
 
$$\widehat{x}_{i} \leftarrow \frac{x_{i} - \mu_{\mathcal{B}}}{\sqrt{\sigma_{\mathcal{B}}^{2} + \epsilon}} \qquad // \text{ normalize}$$
 
$$y_{i} \leftarrow \gamma \widehat{x}_{i} + \beta \equiv \text{BN}_{\gamma,\beta}(x_{i}) \qquad // \text{ scale and shift}$$

### Batch Norm vs Instance Norm

#### Batch Norm:

$$y_{tijk} = \frac{x_{tijk} - \mu_i}{\sqrt{\sigma_i^2 + \epsilon}}, \quad \mu_i = \frac{1}{HWT} \sum_{t=1}^{T} \sum_{l=1}^{W} \sum_{m=1}^{H} x_{tilm}, \quad \sigma_i^2 = \frac{1}{HWT} \sum_{t=1}^{T} \sum_{l=1}^{W} \sum_{m=1}^{H} (x_{tilm} - mu_i)^2.$$

### Instance Norm:

$$y_{tijk} = \frac{x_{tijk} - \mu_{ti}}{\sqrt{\sigma_{ti}^2 + \epsilon}}, \quad \mu_{ti} = \frac{1}{HW} \sum_{l=1}^{W} \sum_{m=1}^{H} x_{tilm}, \quad \sigma_{ti}^2 = \frac{1}{HW} \sum_{l=1}^{W} \sum_{m=1}^{H} (x_{tilm} - mu_{ti})^2.$$