Flags

Flag	Short Default	Help
config-file	repository.config	Specify the config file to use
[no-]help	false	Show context-sensitive help (also try –help-long and –help-man).
[no-]help-full	false	Show help for all commands, including hidden
password	-р	Repository password.
[no-]persist-credentials	true	Persist credentials
[no-]use-keyring	false	Use Gnome Keyring for storing repository password.
adaptive-estimation- threshold	300000	[ADV] Sets the threshold below which the classic estimation method will be used
advanced-commands		[ADV] Enable advanced (and potentially dangerous) commands.
[no-]auto-maintenance	true	[ADV] Automatic maintenance
[no-]caching	true	[ADV] Enables caching of objects (disable with –no-caching)
[no-]completion-bash	false	[ADV] Output possible completions for the given args.
[no-]completion-script-bash	false	[ADV] Generate completion script for bash.
[no-]completion-script-zsh	false	[ADV] Generate completion script for ZSH.
[no-]disable-internal-log	false	[ADV] Disable internal log
[no-]dump-allocator-stats	false	[ADV] Dump allocator stats at the end of execution.
[no-]enable-jaeger-collector	false	[ADV] (DEPRECATED) Emit OpenTelemetry traces to Jaeger collector
[no-]enable-pprof	false	[ADV] Expose pprof handlers
error-notifications	non-interactive	[ADV] Send notification on errors
[no-]help-long	false	[ADV] Generate long help.

Flag	Short Default	Help
[no-]help-man	false	[ADV] Generate a man page.
initial-update-check-delay	24h	[ADV] Initial delay before first time update check
[no-]list-caching	true	[ADV] Enables caching of list results (disable with –no-list-caching)
metrics-directory		[ADV] Directory where the metrics should be saved when kopia exits. A file per process execution will be created in this directory
metrics-listen-addr		[ADV] Expose Prometheus metrics on a given host:port
metrics-push-addr		[ADV] Address of push gateway
metrics-push-format		[ADV] Format to use for push gateway
metrics-push-grouping		[ADV] Grouping for push gateway
metrics-push-interval	5s	[ADV] Frequency of metrics push
metrics-push-job	kopia	[ADV] Job ID for to push gateway
metrics-push-password		[ADV] Password for push gateway
metrics-push-username		[ADV] Username for push gateway
[no-]otlp-trace	false	[ADV] Send OpenTelemetry traces to OTLP collector using gRPC
[no-]profile-blocking	false	[ADV] Enable block profiling
[no-]profile-cpu	false	[ADV] Enable CPU profiling
profile-dir		[ADV] Write profile to the specified directory
profile-memory		[ADV] Enable memory profiling
[no-]profile-mutex	false	[ADV] Enable mutex profiling
[no-]progress	true	[ADV] Enable progress bar

Flag	Short Default	Help
progress-estimation-type	classic	[ADV] Set type of estimation of the data to be snapshotted
progress-update-interval	300ms	[ADV] How often to update progress information
timezone		[ADV] Format time according to specified time zone (local, utc, original or time zone name)
[no-]trace-storage	true	[ADV] Enables tracing of storage operations.
track-releasable		[ADV] Enable tracking of releasable resources.
update-available-notify- interval	1h	[ADV] Interval between update notifications
update-check-interval	168h	[ADV] Interval between update checks
[no-]upgrade-no-block	false	[ADV] Do not block when repository format upgrade is in progress, instead exit with a message.
upgrade-owner-id		[ADV] Repository format upgrade owner-id.