QUICK REFERENCE





(C) 1985 POLAR ENGINEERING
Retyped by hackerb9, 2026

# CLEUSEAU TEXT
## QUICK REFERENCE

### Filing

**F2**.....Load from file
**F3**.....Save to file
**CTRL_V**..Verify file with saved file

### Mode setting

**LABEL**...Toggle label line on/off
**CTRL_J**..Toggle Cleuseau TEXT on/off
**CTRL_O**..Toggle INSERT/OVERWRITE

### Moving

**←**.....Move left one char
**SHIFT←**..Move to start of word (prev)
**CTRL_A**
**CTRL←**...Move to start of line
**CTRL_Q**
**→**.....Move right one char
**SHIFT→**..Move to start of word (next)
**CTRL_F**
**CTRL→**...Move to end of line
**CTRL_R**
**↑**.....Move up one line
**SHIFT↑**..Move to top of screen
**CTRL_T**
**CTRL↑**...Move to top of file
**CTRL_W**
**↓**.....Move down one line
**SHIFT↓**..Move to bottom of screen
**CTRL_B**
**CTRL↓**...Move to end of file
**CTRL_Z**
**CTRL_G**..Go to the next line

### Character editing

**BKSP**....Delete char left of cursor.
**CTRL_H**
**DEL**.....Delete char under cursor
**ENTER**...Insert CR and line feed
**TAB**.....Insert tab to column 1,9,17,..
**CTRL_I**
**CTRL_P**..Insert control char

### Searching and replacing

**F1**.....Search forwards
**F4**.....Search backwards
**CTRL_N**..Search for next string
**CTRL_S**..Replace and search (**PAUSE**)
**CTRL_Y**..Repeat replace and search

### Selecting and pasting

**F7**.....Set select marker at cursor
**F5**.....Copy selection to paste buffer
**F6**.....Cut selection to paste buffer
**CTRL_E**..Append to paste buffer
**CTRL_L**..Lowercase selection
**CTRL_U**..Uppercase selection
**PASTE**...Insert copy of paste buffer

### Miscellaneous

**BREAK**...Cancel any command (**CTRL_C**)
**ESC**.....***n*** times, repeat command
**F8**.....MENU or BASIC (exit TEXT)
**PRINT**...Print screen on printer
**SHIFT_PRINT**..Print file on printer
**CTRL_D**..Display # of bytes/words/lines
**CTRL_X**..HELP (**CTRL_X** **CTRL_X** for all)

# BASIC INSPECTOR
## QUICK REFERENCE

### Editing

**.RENUM** ***<range>*****[TO*****<num>*****][STEP*****<num>*****]...**
Renumber range of lines.
**.MOVE** ***<range>*****[TO*****<num>*****][STEP*****<num>*****]...**
Move the range of lines.
**.COPY** ***<range>*****[TO*****<num>*****][STEP*****<num>*****]...**
Copy range of lines.
**.MIN [*****<num>*****]...**Minimize program size.
**.DELCOM** ***<range>*****..**Delete comments in range.
**.SQUASH** ***<range>*****..**Unnecessary blanks, end quotes and semi-colons removed.
**.PACK** ***<range>*****[LEN*****<num>*****]...**Pack program.
**.EXPAND** ***<range>*****...**Unpack program lines.
**.KILL** ***<range>*****..**Delete lines in range. (Doesn't update line #s.)

### Debugging

**.STOP** ***<range>*****[=*****<string>*****]...**Insert stop points. Shown as |.
**.PRINT** ***<range>*****[=*****<string>*****]..**Insert print points. Shown as _.
**.CONT** ***<range>*****[=*****<string>*****]...**Insert continue points. Shown as ~.
**.OFF** ***<range>*****[=*****<string>*****]....**Delete stop, print or continue points.
**.LOG**.....Print pt log to screen.
**.LOG [*****<num>*****]..**Print pt log file num.
**.LLOG**.....Print pt log to printer.

### Miscellaneous

**CTRL_U**.....Delete input Line.
**CTRL_X**.....HELP. BASIC Inspector.
**ESC**.....Next line number.
**.FILES**.....Files & sizes (screen).
**.LFILES**.....Files & sizes (printer).
**.LIST*****<range>*****[=*****<string>*****]..**Lines in range with ***<string>*** (screen).
**.LLIST*****<range>*****[=*****<string>*****]**.Lines in range with ***<string>*** (printer).
**.STEP** ***<num>*****...**Set auto line num step.
**. (dot)**.....List next line to execute and the GOSUB/RETURN stack.

# GETTING STARTED

To install Cleuseau's software after a cold restart:

| | |
|---|---|
| M100 | **CALL 63012** |
| T200 | **CALL 61167,2** |
| NEC | **EXEC 62393** |

"Cleuseau" will appear in the lower right corner of the menu.

To disable Cleuseau, as if it were cold restarted or removed:

| | |
|---|---|
| M100 | **CALL 913,145** |
| T200 | **CALL 921,146** |
| NEC | **EXEC 1124,145** |

---

## TEXT examples

To move to the 100th line in the file:

**CTRL_↑** **ESC** **99** **ENTER** **CTRL_G**

To count the number of bytes, words, or lines in the file:

**CTRL_↓** **CTRL_D**

To count the number of times a word occurs in the file:

**CTRL_↑** **ESC** R **ENTER** **F1** ***<word>*****ENTER**

To replace & search, checking each time

**CTRL_S** ***<string>*****ENTER** ***<string>*****ENTER**

first ***<string>*** = search string
second ***<string>*** = replace string

At each occurrence press:

**CTRL_N** to search (skip)
**CTRL_Y** to replace and search

Use **F1** and **F4** to control the search direction.

# BASIC examples

To reduce a program to its minimum size

```
.MIN [<num>]
Sure? Y
```

where ***<num>*** is the maximum line length desired.

To stop before executing line 10000:

```
.STOP 10000
```

To stop before any assignment to X:

```
.STOP =X=
```

To list all lines that assign X a value

```
.LIST =X=
```

To list all lines that GOSUB 1000:

```
.LIST =GOSUB 1000
```

To log entire program execution:

```
.PRINT
```

**To** log execution for lines 0 to **999:**

```
.PRINT -999
```

Log lines that start or end a FOR loop:

```
.PRINT =FOR
.PRINT =NEXT
```

To trace program execution on printer:

```
.LLOG
.PRINT
RUN
```

To change all stop pts to continue pts:

```
.CONT =|
```

To change all print pts to continue pts:

```
.CONT =_
```